

Silk Test 15.5

Installation Guide

Micro Focus
575 Anton Blvd., Suite 510
Costa Mesa, CA 92626

Copyright © Micro Focus 2014. All rights reserved. Portions Copyright © 1992-2009 Borland Software Corporation (a Micro Focus company).

MICRO FOCUS, the Micro Focus logo, and Micro Focus product names are trademarks or registered trademarks of Micro Focus IP Development Limited or its subsidiaries or affiliated companies in the United States, United Kingdom, and other countries.

BORLAND, the Borland logo, and Borland product names are trademarks or registered trademarks of Borland Software Corporation or its subsidiaries or affiliated companies in the United States, United Kingdom, and other countries.

All other marks are the property of their respective owners.

2014-06-06

Contents

| | |
|--|-----------|
| Introduction | 5 |
| System Requirements and Prerequisites | 5 |
| Hardware Requirements | 5 |
| Software Requirements | 5 |
| Tested Software | 5 |
| Administrator Privileges | 7 |
| Items Included with Silk Test | 7 |
| Licensing Information | 9 |
| Silk Test Licensing | 10 |
| Generating a Silk Test License Policy | 10 |
| Finding the Host ID | 10 |
| Silk Meter Installation | 10 |
| Uninstalling a Previous Version of Silk Meter | 11 |
| Installing Silk Meter on Your License Server | 11 |
| Modifying Your License Server Configuration | 12 |
| Installing Silk Test | 13 |
| Installation Prerequisites | 13 |
| Resetting the TEMP Environment Variable | 13 |
| Downloading the Silk Test Executable File | 13 |
| Installing the Standard Suite of Silk Test Products | 14 |
| Installing the Complete Suite of Silk Test Products | 16 |
| Installing Silk Test Workbench | 19 |
| Installing Silk4J | 21 |
| Installing the Silk4J Eclipse Plug-in Manually | 23 |
| Enabling and Disabling Rumba | 23 |
| Installing Silk4NET | 24 |
| Installing the Silk4NET Visual Studio Plug-in Manually | 26 |
| Installing Silk Test Classic | 26 |
| Installing Silk Test Runtime or the Silk Test Agents | 28 |
| Installing the Classic Agent for Unix | 30 |
| Uninstalling Silk Test | 31 |
| Silk Test Silent Mode Installation | 31 |
| Creating a Silent Installation Properties File | 31 |
| Setting Up the Silent Installer | 33 |
| Using the Web Installer to Install in Silent Mode | 35 |
| Using the Installation CD to Install in Silent Mode | 35 |
| Verifying the Success of the Silent Installer | 36 |
| Viewing Error Codes | 37 |
| Uninstalling in Silent Mode | 38 |
| What To Do Next | 38 |
| Configuring a Silk Test Workbench Database | 39 |
| Configuring an SQL Server Database Overview | 39 |
| Creating a New SQL Server Database | 39 |
| Creating a New SQL Server Admin User | 39 |
| Setting Up Users in SQL Server | 40 |
| Preparing the SQL Server Silk Test Workbench Database | 41 |
| Configuring an Oracle Database Overview | 41 |
| Selecting an Authentication Method | 41 |
| Creating a New Oracle Database | 43 |
| Setting Up Oracle Authentication | 43 |

| | |
|---|----|
| Setting Up the Oracle Client | 44 |
| Preparing the Oracle Database for Client Connectivity | 44 |
| Setting Up Users for Silk Test Workbench in Oracle | 45 |
| Preparing the Oracle Database | 46 |
| Setting Up a SQL Server or Oracle Database Without a Domain | 47 |
| Creating Users Without a Domain | 47 |
| Setting Up SQL Server Without a Domain | 47 |
| Setting Up an Oracle Database Without a Domain | 48 |
| Creating a Data Source Name Overview | 48 |
| Creating a Data Source Name for an Access Database | 48 |
| Creating a Data Source Name for a SQL Server Database | 49 |
| Creating a Data Source Name for an Oracle Database | 49 |
| Connecting to a Database Overview | 50 |
| Logging On | 50 |
| Changing Your Logon Password | 51 |
| Configuring a Database Connection | 51 |

Introduction

This Help provides all the information you need to install and uninstall Silk Test. It describes hardware and software requirements and details the various setup options.

System Requirements and Prerequisites

The following section identifies the system requirements for installing and running Silk Test.

Hardware Requirements

We recommend the following hardware requirements:

| System Area | Requirement |
|-----------------|--|
| Processor | Intel or AMD DualCore processor running at 2 GHz |
| RAM | 2 GB |
| Hard disk space | 2 GB of free disk space |

Software Requirements

To install and execute Silk Test, the following software needs to be installed:

- Microsoft .NET Framework 4 (Full setup)

Tested Software

This section lists the software with which Silk Test 15.5 has been tested.

Operating Systems



Silk Test 15.5 has been tested with the following operating systems:

- Microsoft Windows XP SP3
- Microsoft Windows Vista SP2
- Microsoft Windows Server 2008
- Microsoft Windows Server 2008 R2
- Microsoft Windows 7
- Microsoft Windows 7 SP1
- Microsoft Windows 8
- Microsoft Windows 8.1
- Microsoft Windows Server 2012

Web Applications

For the Open Agent, Silk Test 15.5 has been tested with the following browsers and Web technologies:

| Technology Type | Tested Version |
|---------------------------------|--------------------------------|
| Mozilla Firefox (playback only) | 22, 23, 24, 25, 26, 27, 28, 29 |

| Technology Type | Tested Version |
|-------------------------------|---|
| Google Chrome (playback only) | 28, 29, 30, 31, 32, 33, 34, 35 |
| Chrome for Android | |
| Stock Android Browser | |
| Apple Safari | |
| Internet Explorer | 8, 9, 10, 11 |
| Android | 4.1, 4.2, 4.3, 4.4 |
| iOS | 7.0, 7.1 |
| Silverlight | 3 (Silverlight Runtime 4), 4 (Silverlight Runtime 4 and Silverlight Runtime 5)  Note: Microsoft has committed to support Silverlight 5.0 until 2021, but has made no concrete announcement about the future roadmap of Silverlight. Whilst we endeavour to maintain the highest levels of support for our customers, we are occasionally limited in the support we can obtain from Microsoft on this platform. |
| Apache Flex | Silk Test 15.5 has been tested with Apache Flex version 3.5 or later using all supported browsers and Adobe AIR 2.0 or later (built with Apache Flex 4.x)  Note: Silk Test does not support testing child domain technologies, including Apache Flex, for Web applications running in Google Chrome. Silk Test supports Adobe Flash Player 10 or later. |
| Java Applets | Silk Test supports Applets for Internet Explorer and Mozilla Firefox. |
| HTML5 | |

Desktop Applications

For the Open Agent, Silk Test 15.5 has been tested with desktop applications that are developed in one of the following technologies:

| Technology Type | Tested Version |
|--|---|
| Java AWT/Swing (including Java Foundation Classes) | Java 1.6, Java 1.7, Java 1.8 |
| Java SWT | Silk Test 15.5 has been tested has been tested with Java SWT version 3.2 or later. Standalone and Rich Client Platform (RCP) applications (SWT standalone applications executed as an applet in the browser are not supported) |
| SAP | SAPGUI client 7.10, SAPGUI client 7.20, SAPGUI client 7.30 |
| Rumba | 8.1, 8.2, 8.3, 9.0, 9.1, 9.2 |
| Win 32 | any |
| WinForms | .NET 3.0, 3.5, 3.5 SP1, 4.0, 4.5 |
| WPF | .NET 3.5 SP1, 4.0, 4.5 |

Silk Test Workbench

Silk Test 15.5 has been tested with the following databases for Silk Test Workbench asset storage:

- Microsoft SQL Server 2008 (SP2) + Express
- Microsoft SQL Server 2012
- Microsoft SQL Server 2012 SP1
- Microsoft SQL Server 2014
- Oracle 11.1
- Oracle 11.2
- Microsoft Access 2000 (as a single-user database)



Note: Micro Focus recommends using Microsoft SQL Server.

Silk4J

You can integrate Silk4J in Eclipse 3.7.2 or later, both 32 and 64 bit. Version 4.3.1 is shipped with Silk Test.

Silk4NET

You can integrate Silk4NET into the following versions of Visual Studio:

- Visual Studio 2010 Professional
- Visual Studio 2012 Professional
- Visual Studio 2013 Professional

Silk Test Classic

Silk Test Classic's Data Driven Workflow has been tested with:

- Text files and comma separated value files (*.txt and *.csv files)
- MS Excel
- MS Access
- MS SQL Server
- Oracle (partial support)
- SyBase SQL Anywhere

Silk Test Classic accesses the preceding databases using ODBC and therefore has been tested with the versions of those databases that have a working ODBC driver.



Note: The Silk Test Classic **Select Data Source** dialog box allows you to choose either the Silk DDA Excel or the Segue DDA Excel data source. For new data driven test cases, choose the Silk DDA Excel data source. Choose the Segue DDA Excel data source for backward compatibility. This allows existing .g.t files that reference Segue DDA Excel to continue to work.

Administrator Privileges

You must have local administrator privileges to install Silk Test. Once Silk Test is properly installed, you must also have administrator privileges in order to perform the following tasks:

- Run Silk Test Classic.
- Configure a database for Silk Test Workbench.

Items Included with Silk Test

When you install Silk Test, the following items are available:

- Silk Test Start Screen, which has direct links to all clients.

- Silk Test Workbench
- Silk Test Classic
- Silk Test Agents
- Silk Test Recorder
- Silk4NET
- Silk4J
- Product Notification Service - This application resides in the system tray and will check for updates at a configurable interval.
- Online Help topics

Access the help from within each product from the **Help** menu.

- Release Notes

For information about new features, supported platforms and versions, known issues, and work-arounds, refer to the [Release Notes](#).

- Tutorials

Access the tutorials from **Start > Programs > Silk > Silk Test > Documentation > Tutorials** or **Help > Tutorials**.

You must have Adobe Acrobat Reader™ to view PDF documents.

- Sample applications that you can access online

- Adobe Flex sample applications

Access Flex sample applications at <http://demo.borland.com/flex/SilkTest15.5/index.html>.

- Insurance Company Web application

Use the Insurance Company Web application with Silk Test Workbench's and Silk Test Classic's tutorials. You can access the Web application at: <http://demo.borland.com/InsuranceWebExtJS/>.



- Green Mountain Outpost (GMO) Web application

Use the GMO application with Silk Test Classic's tutorials. You can access the Web application at: <http://demo.borland.com/gmopost>.

Licensing Information

Unless you are using a trial version, Silk Test requires a license.

The licensing model is based on the client that you are using and the applications that you want to be able to test. The available licensing modes support the following application types:

| Licensing Mode | Application Type |
|----------------|--|
| Full | <ul style="list-style-type: none">• Web applications, including the following:<ul style="list-style-type: none">• Apache Flex• Java-Applets• Mobile Web applications.<ul style="list-style-type: none">• Android• iOS• Apache Flex• Java AWT/Swing• Java SWT and Eclipse RCP• .NET, including Windows Forms and Windows Presentation Foundation (WPF)• Rumba• Windows API-Based <p> Note: To upgrade your license to a Full license, visit www.borland.com.</p> |
| Premium | <p>All application types that are supported with a <i>Full</i> license, plus SAP applications.</p> <p> Note: To upgrade your license to a Premium license, visit www.borland.com.</p> |

Silk Test Licensing

This section describes how to obtain a license policy for Silk Test and how to install Silk Meter. You must have administrator privileges to install Silk Meter.



Note: Silk Test requires Silk Meter version 2008 or later as well as a Silk Test license policy.

Install Silk Meter once per license server. If you have multiple license servers, you need multiple license policy files, each one tied to a particular license server. A single Silk Meter license server can administer license policies for multiple products.

If you have received a Silk Test license policy, install the license policy on your license server. If you have not received a license policy, generate a license policy.

Generating a Silk Test License Policy

You need a license policy to run Silk Test. You can use our online license generator to generate a license policy. The online license generator requires an SSL-capable browser, such as Firefox or Internet Explorer. You will receive an email with instructions on how to generate your license policy. If you did not receive these instructions, contact customer care at <http://support.microfocus.com>.

Finding the Host ID

1. On the license server, open a command prompt and enter the command `ipconfig/all`. The license server lists its connection addresses.
2. Note the host ID, which is the `MAC Address or Physical Address` of your LAN card, such as `00-BF-00-1C-D3-3D`.

You must enter this information to obtain a license policy for Silk Test .



Tip: Depending on your system setup, including virtual machines and VPN connections, your computer might have several MAC addresses. Be sure to note the host ID of your physical LAN card.

Silk Meter Installation

If you have the Silk Test license policy, you can install it when you install Silk Meter. To obtain a Silk Test license policy, access the online License Generator to generate a license policy.

A Silk Test license policy is not required to install Silk Meter on your license server. Using the Silk Meter **User Policy Administrator**, you can import the Silk Test license policy later. However, you must import the license policy before you can run Silk Test .

Install Silk Meter once per license server. If you have multiple license servers, you need multiple license policy files, each one tied to a particular license server. A single Silk Meter license server can administer license policies for multiple products.

Silk Meter License Server Requirements

Before installing Silk Meter, refer to the *Release Notes* to ensure that the license server meets the requirements.

Uninstalling a Previous Version of Silk Meter

If Silk Meter is installed on the license server, you must uninstall it before installing the latest version of Silk Meter.

1. Choose **Start > Programs > Silk > Silk Meter > Uninstall**.
2. Click **Yes** to uninstall Silk Meter. The **Remove Settings** dialog box opens.
3. Click **No** to keep your Silk Meter settings.



Attention: You must click **No** to preserve license policies that currently exist on your Silk Meter license server.

4. Reboot your computer.

Silk Meter is uninstalled, and you can install the latest version of Silk Meter.

Installing Silk Meter on Your License Server

Before installing Silk Meter, verify the following information:

- Your user account possesses administrator privileges.
 - An instance of Silk Meter is not installed on your license server.
1. Locate the Silk Meter executable file `silkmeter-150.exe` and perform the appropriate steps, as follows:
 - If you have a Silk Test CD, insert the CD. If the setup program does not start automatically, manually start the Silk Meter setup program by choosing **Start > Run** and entering `<cd drive>:\Silk Meter\silkmeter-150.exe`.
 - If you have already downloaded Silk Meter, perform the following steps:
 1. Navigate to the location where you saved the EXE file.
 2. Double-click the EXE file.
 - If you are downloading Silk Meter:
 1. Visit the [product updates site](#) and search for Silk Meter.
 2. Download and save the latest **Silk Meter Installation Files**.
 3. Specify the location to which you want to save this file, and then click **Save**.

Alternative: Run the file from your browser.
 4. Navigate to the location where you saved the EXE file.
 5. Double-click the EXE file.

The Silk Meter installation wizard opens, displaying the **Copyright Information** page.

2. Click **Next** to continue. Setup extracts the files to a temporary directory.
3. Click **Next** to continue. The **License Agreement** page displays.
4. Read the license agreement carefully. If you accept the terms of the agreement, click **Yes** to continue. The **Enter Installation Path and Configuration Directory for Silk Meter Runtime** page opens.
5. Click **Next** to install Silk Meter in the default directory and to use the default configuration folder, `\cfg`. The **Enter Host Name** page opens.
6. Enter or verify the hostname and port, then click **Next**.



Note: The hostname is the name of the computer on which Silk Meter is installed.

The **Select Program Folder** page opens.

7. In the **Program Folders** text box, accept the default program folder, `Silk\Silk Meter`, or specify a different program folder, and then click **Next** to continue. Setup installs Silk Meter. Upon completion, the **Install Silk Meter Policy** page opens.
 8. Perform one of the following steps:
 - If you already have a Silk Test license policy, click [...] to navigate to the location where you saved the Silk Test license policy file, `license.pol`, and then click **Open**. Click **Finish** to install the Silk Test license policy.
 - If you do not have a Silk Test license policy, click **Finish**. You can import the Silk Test license policy when you receive it. Instructions for importing Silk Test license files are available from the online License Generator and in Silk Meter Runtime Help.
- The **View Release Notes** page opens.
9. Click **Yes** to view the Silk Meter Release Notes, or click **No** to continue the installation without viewing the release notes. The **InstallShield Wizard Complete** page opens.
 10. Click **Finish** to complete the installation process.



Important: If setup prompts you to restart the computer, make sure to do so.

Modifying Your License Server Configuration

Use the **Select Silk Meter License Server** utility to modify or repair your license server configuration. This utility is installed with your Silk Test installation and checks your local system for the existence of Silk Meter license server configuration files. If the files are found, the configuration and type of license server are displayed and used for licensing. If no configuration data is found, the **Select Silk Meter License Server** dialog box displays the default settings.

1. Choose **Start > Programs > Silk > Silk Test > Administration Tools > Change your License Server Configuration**. The **Select Silk Meter License Server** utility opens.
2. In the **Application** list box, select the product for which you want to configure the license server.
3. Click the **Using local or remote server** option button to configure a Silk Meter license server.
4. In the **License Server Host** text box, type the computer name for the Silk Meter license server. Unless your network administrator has defined a different port, do not change the **Port Number**.
5. Click **Apply** to generate the license server configuration.
6. Click **Test Connection** to verify that a Silk Meter server is accessible on the specified host and port. If the connection is successful, the **Status** text box displays a `SUCCESS` message.



Note: In some cases, specifying the simple name of the license server in the **License server host** text box, such as `licenseserver`, might not work. A message box stating `Connection to Silk Meter license server failed` opens. To resolve this issue, specify the hostname by using a fully qualified name, such as `licenseserver.mycompany.com`.

7. Click **Close** to complete the license server configuration.

Installing Silk Test

This section explains the setup options that are available when installing Silk Test.

Installation Prerequisites

Before installing Silk Test, verify the following information:

- Your user account possesses local administrator privileges.
- The file `msvcp60.dll` is installed in the Windows System32 directory (`windows\system32` or `winnt\system32`).

This file is installed automatically as part of the standard Windows installation. If `msvcp60.dll` is not in your System32 directory, use Windows Explorer to search for the file, then copy it to the System32 directory. If you cannot find this file on your system, search for the file on your installation CD, or upgrade to the latest service pack.

- On Windows 2008 R2 64-bit machines, ensure that .NET 3.5 SP1 is installed.

You can install the **.NET Framework 3.5.1 Features** from the **Add Features Wizard** in **Server Manager**. Or you can download it from the Microsoft Web site.



Note: To use .NET Framework with a server system, for example Windows Server 2008, enable the .NET Framework in **Server Manager**. If you do not enable the .NET Framework, a dialog box opens, which states that you must use the Role Management Tool, and the Silk Test setup process stops.

Resetting the *TEMP* Environment Variable

If your Windows *TEMP* environment variable does not point to a valid directory, an error message is displayed. To successfully install Silk Test, your *TEMP* environment variable must point to a valid directory.

1. Choose **Start > Settings > Control Panel**.
2. Double-click **System**.
3. Click the **Advanced** tab, and then click **Environment Variables**.
4. Under **User Variables** or **System Variables**, double-click the *TEMP* variable.
5. Enter a valid directory, and then click **OK**.
6. Restart the Silk Test installation by double-clicking the EXE file.

Downloading the Silk Test Executable File

Download the Silk Test executable file if you do not have the installation CD.

1. Navigate to <http://supportline.microfocus.com/>.
2. Type your customer ID and password in the **User Name** and **Password** text boxes.
3. Click **Submit** and then navigate to Silk Test and select the version that you want to install.
4. Specify the location to which you want to save this file, and then click **Save**.

Alternative: Run the file from your browser by double-clicking the EXE file.

Use the executable file to install Silk Test.

Installing the Standard Suite of Silk Test Products

Before you start, download the Silk Test executable file or insert the SilkTest CD into the CD drive.

Install the standard installation of Silk Test, including Silk Test Workbench, the Silk Test Agents, Silk Test Recorder, Silk4J, and Silk4NET. The standard installation enables you to record, script, execute, and view the results of tests.

1. Locate and double-click the Silk Test executable file.

If you have a Silk Test CD, insert your CD. If the setup program does not start automatically, manually start the Silk Test setup program by choosing **Start > Run** and entering `<cddrive>:\setup.exe`.



Note: If your Windows *TEMP* environment variable does not point to a valid directory, an error message is displayed. To successfully install Silk Test, your *TEMP* environment variable must point to a valid directory.

The **InstallAnywhere** wizard opens.

2. If a previous version of Silk Test is installed, click **Uninstall** and then click **Next** to remove all installed features.

You must uninstall any earlier versions before you install a new version.

3. Click **Next**. The **License Agreement** opens.
4. Read the license agreement carefully. If you accept the terms of the agreement, click **I accept the terms of the License Agreement**.
5. Click **Next**. The **Choose Install Set** page opens.
6. Select **Standard** from the list.

The standard installation enables you to record, script, execute, and view the results of tests and it is the default setting.

7. To include additional shortcut icons, check one or both of the following check boxes:

- **On the Desktop** – Adds icons to the desktop.
- **In the Quick Launch Bar** – Adds icons to the Quick Launch toolbar.

8. Click **Next**. The **Choose Install Folder** page opens.

9. To change the default installation directory, perform the following steps:

- a) Click **Choose**. The **Browse For Folder** dialog box opens.
- b) Specify the folder in which you want to install Silk Test, and then click **OK** to return to the **Choose Install Folder** page.



Note: Silk Test must be installed on a local drive. An error message appears if you specify an invalid installation destination.

The location displays in the **Where Would You Like to Install?** text box.

10. Click **Next**. The **Welcome to Silk4J** page opens.

11. Specify whether you want to install a new Eclipse environment when you install Silk4J.

- a) Click one of the following option buttons:

- **Download Eclipse (92MB) and install Silk4J** – To install Silk4J and an Eclipse 3.7.2 environment, click this option.
- **Install Silk4J and use an existing Eclipse environment** – To use an existing Eclipse environment with Silk4J, click this option. Click **Browse** and navigate to the Eclipse environment that you want to use.
- **Install Silk4J manually** – To install Silk4J into an Eclipse environment manually, click this option. A folder named `dropins` is created in the Silk Test installation directory. Copy this folder into a valid Eclipse directory to use Silk4J.

b) Click **Next**.

When installation completes, access the Eclipse environment by choosing **Start > Programs > Silk > Silk Test > Clients > Silk4J**. For instructions for using the plug-in, refer to the online help within the plug-in.

12. Specify whether you want to install Silk4NET for use with an existing Visual Studio environment.

The Silk4NET Visual Studio plug-in enables you to create VB.NET or C# test scripts directly in Visual Studio.

a) Click one of the following option buttons:

- **Install Silk4NET and use an existing Visual Studio 2010 or later** – To use an existing Visual Studio 2010 or later environment, click this option.
- **Install Silk4NET manually** – To complete the installation of Silk4NET at a later time, click this option. If Visual Studio 2010 or later is not installed on your machine, you must choose this option. Refer to *Installing Silk4NET Visual Studio Plug-in Manually* later in this guide for instructions.

b) Click **Next**.

When you start Visual Studio, a menu option appears for Silk4NET and the Silk4NET project is available from the **Installed Templates** list.

13. Specify whether you want to create Windows firewall exceptions.



Note: This step is only available for Windows XP, Windows Vista, Windows 7, and Windows Server 2008.

a) Click one of the following option buttons:

- **Yes** – To have setup create firewall exceptions for all Silk Test executable files. As a result, you are not prompted to block or allow the executable files when you launch them.
- **No** – To be prompted when you launch the Silk Test executable file.

b) Click **Next**.

14. Review the provided information and perform one of the following steps:

- To change any settings, click **Previous** to return to the appropriate page.
- If you are satisfied with the settings, click **Install** to start the installation process.



Tip: If a message appears stating that there is not enough space while files are copying, redefine the TEMP area to a drive that contains more space. The installer uses the TEMP area for unzipping files. For example, if your TEMP area is `d:\temp` and you are installing to `e:\SilkTest`, the E drive may contain enough space for the installation, but the D drive is the limiting factor.

The status bar provides information about the installation process. Upon completion, the **Choose Licensing Mode** page opens.

15. Click one of the following option buttons:

- **Evaluation** Installs an evaluation version of Silk Test, which enables you to explore the full product functionality for 45 days.
- **Full version** – Installs an unrestricted version of Silk Test, which requires a license.

16. The **Select Silk Meter License Server** dialog box opens. This utility checks your local system for the existence of Silk Meter license server configuration files. If the files are found, the configuration and type of license server are displayed and are used for licensing. If no configuration data is found, the **Select SilkMeter License Server** dialog box is displayed with the default settings. Click one of the following option buttons:

Using local or remote server

In the **License Server Host** text box, enter the name of the computer on which Silk Meter is installed. The default **Port**, 5461, should not be changed, unless your network administrator has defined a different port. Click **Test Connection** to verify

that a Silk Meter server is accessible on the specified host and port. Testing the connection to the license server may fail during installation as required system libraries, which will be installed later with the software package, may not yet be available.



Note: In some cases, specifying the simple name of the license server in the **License Server Host** text box, such as `licenseserver`, might not work. A message box stating there is no license server running on the hostname you specified opens. To resolve this issue, specify the hostname by using a fully qualified name, such as `licenseserver.mycompany.com`.

Using a standalone license

Runs Silk Meter standalone. You are prompted to import a Silk Meter license file. Click **Yes** and specify the location of your license file.



Note: You can import your license file later. Click **Close** to skip this step. The **Select Silk Meter License Server** utility is installed with the product, so that you can access it later from the **Start** menu to test the connection.

17. Click **Next**.



Fastpath: A working network connection is required when running Silk Test with a remote Silk Meter license server. If you need to verify that the network is working, choose **Start > Run**, and then type `ping localhost` or `ping <license server name>`, or open a command prompt and type either of those commands.

18. Click **Done**.

Installing the Complete Suite of Silk Test Products

Before you start, download the Silk Test executable file or insert the SilkTest CD into the CD drive.

Install the complete installation of Silk Test. The complete installation includes Silk Test Classic, Classic Agent, and Silk TrueLog Explorer in addition to Silk Test Workbench, the Silk Test Open Agent, Silk Test Recorder, Silk4J, and Silk4NET.

1. Locate and double-click the Silk Test executable file.

If you have a Silk Test CD, insert your CD. If the setup program does not start automatically, manually start the Silk Test setup program by choosing **Start > Run** and entering `<cddrive>:\setup.exe`.



Note: If your Windows *TEMP* environment variable does not point to a valid directory, an error message is displayed. To successfully install Silk Test, your *TEMP* environment variable must point to a valid directory.

The **InstallAnywhere** wizard opens.

2. If a previous version of Silk Test is installed, click **Uninstall** and then click **Next** to remove all installed features.

You must uninstall any earlier versions before you install a new version.

3. Click **Next**. The **License Agreement** opens.

4. Read the license agreement carefully. If you accept the terms of the agreement, click **I accept the terms of the License Agreement**.

5. Click **Next**. The **Choose Install Set** page opens.

6. Select **Complete** from the list.

The complete installation enables you to record, script, execute, and view the results of tests.

Checkmarks display next to each option except Silk Test Runtime.



Note: The complete installation includes the Silk Test Windows and .NET extension kits, which are included as part of the Silk Test Classic Agent installation.

7. To include additional shortcut icons, check one or both of the following check boxes:

- **On the Desktop** – Adds icons to the desktop.
- **In the Quick Launch Bar** – Adds icons to the Quick Launch toolbar.

8. Click **Next**. The **Choose Install Folder** page opens.

9. To change the default installation directory, perform the following steps:

- a) Click **Choose**. The **Browse For Folder** dialog box opens.
- b) Specify the folder in which you want to install Silk Test, and then click **OK** to return to the **Choose Install Folder** page.



Note: You cannot install Silk Test and Silk Test Runtime on the same machine.



Note: Silk Test must be installed on a local drive. An error message appears if you specify an invalid installation destination.

The location displays in the **Where Would You Like to Install?** text box.

10. Click **Next**. The **Welcome to Silk4J** page opens.

11. Specify whether you want to install a new Eclipse environment when you install Silk4J.

- a) Click one of the following option buttons:
 - **Download Eclipse (92MB) and install Silk4J** – To install Silk4J and an Eclipse 3.7.2 environment, click this option.
 - **Install Silk4J and use an existing Eclipse environment** – To use an existing Eclipse environment with Silk4J, click this option. Click **Browse** and navigate to the Eclipse environment that you want to use.
 - **Install Silk4J manually** – To install Silk4J into an Eclipse environment manually, click this option. A folder named `dropins` is created in the Silk Test installation directory. Copy this folder into a valid Eclipse directory to use Silk4J.

b) Click **Next**.

When installation completes, access the Eclipse environment by choosing **Start > Programs > Silk > Silk Test > Clients > Silk4J**. For instructions for using the plug-in, refer to the online help within the plug-in.

12. Specify whether you want to install Silk4NET for use with an existing Visual Studio environment.

The Silk4NET Visual Studio plug-in enables you to create VB.NET or C# test scripts directly in Visual Studio.

a) Click one of the following option buttons:

- **Install Silk4NET and use an existing Visual Studio 2010 or later** – To use an existing Visual Studio 2010 or later environment, click this option.
- **Install Silk4NET manually** – To complete the installation of Silk4NET at a later time, click this option. If Visual Studio 2010 or later is not installed on your machine, you must choose this option. Refer to *Installing Silk4NET Visual Studio Plug-in Manually* later in this guide for instructions.

b) Click **Next**.

When you start Visual Studio, a menu option appears for Silk4NET and the Silk4NET project is available from the **Installed Templates** list.

13. Specify whether you want to create Windows firewall exceptions.



Note: This step is only available for Windows XP, Windows Vista, Windows 7, and Windows Server 2008.

a) Click one of the following option buttons:

- **Yes** – To have setup create firewall exceptions for all Silk Test executable files. As a result, you are not prompted to block or allow the executable files when you launch them.
- **No** – To be prompted when you launch the Silk Test executable file.

b) Click **Next**.

14. Review the provided information and perform one of the following steps:

- To change any settings, click **Previous** to return to the appropriate page.
- If you are satisfied with the settings, click **Install** to start the installation process.



Tip: If a message appears stating that there is not enough space while files are copying, redefine the TEMP area to a drive that contains more space. The installer uses the TEMP area for unzipping files. For example, if your TEMP area is `d:\temp` and you are installing to `e:\SilkTest`, the E drive may contain enough space for the installation, but the D drive is the limiting factor.

The status bar provides information about the installation process. Upon completion, the **Choose Licensing Mode** page opens.

15. Click one of the following option buttons:

- **Evaluation** Installs an evaluation version of Silk Test, which enables you to explore the full product functionality for 45 days.
- **Licensed** – Installs an unrestricted version of Silk Test, which requires a license.

16. The **Select Silk Meter License Server** dialog box opens. This utility checks your local system for the existence of Silk Meter license server configuration files. If the files are found, the configuration and type of license server are displayed and are used for licensing. If no configuration data is found, the **Select Silk Meter License Server** dialog box is displayed with the default settings. Click one of the following option buttons:

Using local or remote server

In the **License Server Host** text box, enter the name of the computer on which Silk Meter is installed. The default **Port**, 5461, should not be changed, unless your network administrator has defined a different port. Click **Test Connection** to verify that a Silk Meter server is accessible on the specified host and port. Testing the connection to the license server may fail during installation as required system libraries, which will be installed later with the software package, may not yet be available.



Note: In some cases, specifying the simple name of the license server in the **License Server Host** text box, such as `licenseserver`, might not work. A message box stating `there is no license server running on the hostname you specified` opens. To resolve this issue, specify the hostname by using a fully qualified name, such as `licenseserver.mycompany.com`.

Using a standalone license

Runs Silk Meter standalone. You are prompted to import a Silk Meter license file. Click **Yes** and specify the location of your license file.



Note: You can import your license file later. Click **Close** to skip this step. The **Select Silk Meter License Server** utility is installed with the product, so that you can access it later from the **Start** menu to test the connection.

17. Click **Next**.



Fastpath: A working network connection is required when running Silk Test with a remote Silk Meter license server. If you need to verify that the network is working, choose **Start > Run**, and then type `ping localhost` or `ping <license server name>`, or open a command prompt and type either of those commands.

18. Specify whether you want to restart the system to complete the installation and then click **Done**.



Attention: You must restart your computer for Silk Test Classic to work properly.

Installing Silk Test Workbench

Silk Test Workbench is the quality testing environment that offers .NET scripting for power users and easy to use visual tests to make testing more accessible to a broader audience. Silk Test Workbench is automatically installed when you choose a complete or standard installation. If you choose a basic installation, you can install Silk Test Workbench without any other components. When you install Silk Test Workbench, the Open Agent is also installed. The Open Agent is required to run Silk Test Workbench.

1. Locate and double-click the Silk Test executable file.

If you have a Silk Test CD, insert your CD. If the setup program does not start automatically, manually start the Silk Test setup program by choosing **Start > Run** and entering `<cddrive>:\setup.exe`.



Note: If your Windows *TEMP* environment variable does not point to a valid directory, an error message is displayed. To successfully install Silk Test, your *TEMP* environment variable must point to a valid directory.

The **InstallAnywhere** wizard opens.

2. If a previous version of Silk Test is installed, click **Uninstall** and then click **Next** to remove all installed features.

You must uninstall any earlier versions before you install a new version.

3. Click **Next**. The **License Agreement** opens.

4. Read the license agreement carefully. If you accept the terms of the agreement, click **I accept the terms of the License Agreement**.

5. Click **Next**. The **Choose Install Set** page opens.

6. Select **Basic** from the list.

The basic installation installs Silk Test Workbench, Silk Test Recorder, and the Open Agent.

7. To include additional shortcut icons, check one or both of the following check boxes:

- **On the Desktop** – Adds icons to the desktop.
- **In the Quick Launch Bar** – Adds icons to the Quick Launch toolbar.

8. Click **Next**. The **Choose Install Folder** page opens.

9. To change the default installation directory, perform the following steps:

- a) Click **Choose**. The **Browse For Folder** dialog box opens.
- b) Specify the folder in which you want to install Silk Test, and then click **OK** to return to the **Choose Install Folder** page.



Note: You cannot install Silk Test and Silk Test Runtime on the same machine.



Note: Silk Test must be installed on a local drive. An error message appears if you specify an invalid installation destination.

The location displays in the **Where Would You Like to Install?** text box.

10. Click **Next**. The **Firewall Exceptions** page opens.

11. Specify whether you want to create Windows firewall exceptions.



Note: This step is only available for Windows XP, Windows Vista, Windows 7, and Windows Server 2008.

- a) Click one of the following option buttons:

- **Yes** – To have setup create firewall exceptions for all Silk Test executable files. As a result, you are not prompted to block or allow the executable files when you launch them.

- **No** – To be prompted when you launch the Silk Test executable file.

b) Click **Next**.

12. Review the provided information and perform one of the following steps:

- To change any settings, click **Previous** to return to the appropriate page.
- If you are satisfied with the settings, click **Install** to start the installation process.



Tip: If a message appears stating that there is not enough space while files are copying, redefine the TEMP area to a drive that contains more space. The installer uses the TEMP area for unzipping files. For example, if your TEMP area is `d:\temp` and you are installing to `e:\SilkTest`, the E drive may contain enough space for the installation, but the D drive is the limiting factor.

The status bar provides information about the installation process. Upon completion, the **Choose Licensing Mode** page opens.

13. Click one of the following option buttons:

- **Evaluation** Installs an evaluation version of Silk Test, which enables you to explore the full product functionality for 45 days.
- **Licensed** – Installs an unrestricted version of Silk Test, which requires a license.

14. The **Select Silk Meter License Server** dialog box opens. This utility checks your local system for the existence of Silk Meter license server configuration files. If the files are found, the configuration and type of license server are displayed and are used for licensing. If no configuration data is found, the **Select Silk Meter License Server** dialog box is displayed with the default settings. Click one of the following option buttons:

Using local or remote server

In the **License Server Host** text box, enter the name of the computer on which Silk Meter is installed. The default **Port**, 5461, should not be changed, unless your network administrator has defined a different port. Click **Test Connection** to verify that a Silk Meter server is accessible on the specified host and port. Testing the connection to the license server may fail during installation as required system libraries, which will be installed later with the software package, may not yet be available.



Note: In some cases, specifying the simple name of the license server in the **License Server Host** text box, such as `licenseserver`, might not work. A message box stating `there is no license server running on the hostname you specified` opens. To resolve this issue, specify the hostname by using a fully qualified name, such as `licenseserver.mycompany.com`.

Using a standalone license

Runs Silk Meter standalone. You are prompted to import a Silk Meter license file. Click **Yes** and specify the location of your license file.



Note: You can import your license file later. Click **Close** to skip this step. The **Select Silk Meter License Server** utility is installed with the product, so that you can access it later from the **Start** menu to test the connection.

15. Click **Next**.



Fastpath: A working network connection is required when running Silk Test with a remote Silk Meter license server. If you need to verify that the network is working, choose **Start > Run**, and then type `ping localhost` or `ping <license server name>`, or open a command prompt and type either of those commands.

16. Click **Done**.

Installing Silk4J

The Silk4J Eclipse plug-in enables you to create Java based test scripts directly in your Eclipse environment. Silk4J is automatically installed when you choose a standard or complete installation. If you choose a basic or custom installation, you can install Silk4J at a later time. When you install Silk4J, Silk Test Recorder and the Open Agent are also installed. Silk Test Recorder enables you to record tests rather than manually coding them. The Open Agent is required to run Silk4J and Silk Test Recorder.

1. Locate and double-click the Silk Test executable file.

If you have a Silk Test CD, insert your CD. If the setup program does not start automatically, manually start the Silk Test setup program by choosing **Start > Run** and entering `<cddrive>:\setup.exe`.



Note: If your Windows *TEMP* environment variable does not point to a valid directory, an error message is displayed. To successfully install Silk Test, your *TEMP* environment variable must point to a valid directory.

The **InstallAnywhere** wizard opens.


2. If a previous version of Silk Test is installed, click **Uninstall** and then click **Next** to remove all installed features.

You must uninstall any earlier versions before you install a new version.

3. Click **Next**. The **License Agreement** opens.
4. Read the license agreement carefully. If you accept the terms of the agreement, click **I accept the terms of the License Agreement**.
5. Click **Next**. The **Choose Install Set** page opens.
6. From the drop-down list, select **Custom** and then check the **Silk4J** check box. Silk4J, Silk Test Recorder, and the Open Agent will be installed.
7. Click **Next**. The **Choose Install Folder** page opens.
8. To change the default installation directory, perform the following steps:
 - a) Click **Choose**. The **Browse For Folder** dialog box opens.
 - b) Specify the folder in which you want to install Silk Test, and then click **OK** to return to the **Choose Install Folder** page.The location displays in the **Where Would You Like to Install?** text box.
9. Click **Next**. The **Welcome to Silk4J** page opens.
10. Specify whether you want to install a new Eclipse environment when you install Silk4J.
 - a) Click one of the following option buttons:
 - **Download Eclipse (92MB) and install Silk4J** – To install Silk4J and an Eclipse 3.7.2 environment, click this option.
 - **Install Silk4J and use an existing Eclipse environment** – To use an existing Eclipse environment with Silk4J, click this option. Click **Browse** and navigate to the Eclipse environment that you want to use.
 - **Install Silk4J manually** – To install Silk4J into an Eclipse environment manually, click this option. A folder named `dropins` is created in the Silk Test installation directory. Copy this folder into a valid Eclipse directory to use Silk4J.
 - b) Click **Next**.

When installation completes, access the Eclipse environment by choosing **Start > Programs > Silk > Silk Test > Clients > Silk4J**. For instructions for using the plug-in, refer to the online help within the plug-in.

11. Specify whether you want to create Windows firewall exceptions.

 **Note:** This step is only available for Windows XP, Windows Vista, Windows 7, and Windows Server 2008.


a) Click one of the following option buttons:

- **Yes** – To have setup create firewall exceptions for all Silk Test executable files. As a result, you are not prompted to block or allow the executable files when you launch them.
- **No** – To be prompted when you launch the Silk Test executable file.

b) Click **Next**.

12. Review the provided information and perform one of the following steps:

- To change any settings, click **Previous** to return to the appropriate page.
- If you are satisfied with the settings, click **Install** to start the installation process.

 **Tip:** If a message appears stating that there is not enough space while files are copying, redefine the TEMP area to a drive that contains more space. The installer uses the TEMP area for unzipping files. For example, if your TEMP area is `d:\temp` and you are installing to `e:\SilkTest`, the E drive may contain enough space for the installation, but the D drive is the limiting factor.

The status bar provides information about the installation process. Upon completion, the **Choose Licensing Mode** page opens.

13. Click one of the following option buttons:

- **Evaluation** Installs an evaluation version of Silk Test, which enables you to explore the full product functionality for 45 days.
- **Full version** – Installs an unrestricted version of Silk Test, which requires a license.

14. The **Select Silk Meter License Server** dialog box opens. This utility checks your local system for the existence of Silk Meter license server configuration files. If the files are found, the configuration and type of license server are displayed and are used for licensing. If no configuration data is found, the **Select Silk Meter License Server** dialog box is displayed with the default settings. Click one of the following option buttons:

Using local or remote server

In the **License Server Host** text box, enter the name of the computer on which Silk Meter is installed. The default **Port**, 5461, should not be changed, unless your network administrator has defined a different port. Click **Test Connection** to verify that a Silk Meter server is accessible on the specified host and port. Testing the connection to the license server may fail during installation as required system libraries, which will be installed later with the software package, may not yet be available.



Note: In some cases, specifying the simple name of the license server in the **License Server Host** text box, such as `licenseserver`, might not work. A message box stating `there is no license server running on the hostname you specified` opens. To resolve this issue, specify the hostname by using a fully qualified name, such as `licenseserver.mycompany.com`.

Using a standalone license

Runs Silk Meter standalone. You are prompted to import a Silk Meter license file. Click **Yes** and specify the location of your license file.



Note: You can import your license file later. Click **Close** to skip this step. The **Select Silk Meter License Server** utility is installed with the product, so that you can access it later from the **Start** menu to test the connection.

15. Click **Next**.



Fastpath: A working network connection is required when running Silk Test with a remote Silk Meter license server. If you need to verify that the network is working, choose **Start > Run**, and

then type `ping localhost` or `ping <license server name>`, or open a command prompt and type either of those commands.

16. Click **Done**.

17. Restart Eclipse if it was running when you performed the Silk4J installation.

When installation completes, access the Eclipse environment by clicking **Start > Programs > Silk > Silk Test > Clients > Silk4J**. For instructions for using the plug-in, refer to the online help within the plug-in.

Installing the Silk4J Eclipse Plug-in Manually

The Silk4J Eclipse plug-in enables you to create Java-based test scripts directly in your Eclipse environment. You can install the Silk4J Eclipse plug-in when you install Silk Test using the Silk Test installation wizard.

Use this procedure:

- If you upgrade your version of Eclipse after you install the Silk4J plug-in.
- If you chose the **Install Silk4J manually** option during installation.
- If you did not install the Silk4J Eclipse plug-in when you installed Silk Test, and you want to install it manually.

1. Perform one of the following steps:

- If you chose the **Install Silk4J Manually** option during installation, locate the `dropins` folder in the Silk Test installation directory.

By default the location is `C:\Program Files\Silk\Silk Test\dropins`.

- Create a `dropins` folder in the Silk Test installation directory and then create a `Silk4J.link` file that contains the following text:

```
path=<Silk Test Install Directory>/ng/Silk4J
```

For example, you might add:

```
path=C:/Program Files/Silk/Silk Test/ng/Silk4J
```



Note: The path requires forward slashes.

2. Copy the `Silk4J.link` file and paste it into the Eclipse `dropins` folder.

For example, if your Eclipse environment is installed at `C:\Eclipse`, copy the `Silk4J.link` file to `C:\Eclipse\dropins`.

3. Restart Eclipse if it was running when you performed the Silk4J installation.

When installation completes, access the Eclipse environment by clicking **Start > Programs > Silk > Silk Test > Clients > Silk4J**. For instructions for using the plug-in, refer to the online help within the plug-in.



Tip: If you encounter problems starting Silk4J, start Eclipse with the parameter `-clean` one time.

Enabling and Disabling Rumba

Rumba is the world's premier Windows desktop terminal emulation solution. Rumba provides connectivity solutions to mainframes, mid-range, UNIX, Linux, and HP servers.

Enabling Support

Before you can record and replay Rumba scripts, you need to enable support:

1. Install Rumba desktop client software version 8.1 or later.
2. Click **Start > Programs > Silk > Silk Test > Administration > Rumba plugin > Enable Silk Test Rumba plugin**.

Disabling Support

Click **Start > Programs > Silk > Silk Test > Administration > Rumba plugin > Disable Silk Test Rumba plugin**.

Installing Silk4NET

The Silk4NET Visual Studio plug-in enables you to create VB.NET or C# test scripts directly in Visual Studio. Silk4NET is automatically installed when you choose a standard or complete installation. If you choose a basic or custom installation, you can install Silk4NET at a later time. When you install Silk4NET, Silk Test Recorder and the Open Agent are also installed. Silk Test Recorder enables you to record tests rather than manually coding them. The Open Agent is required to run Silk4NET and Silk Test Recorder.

1. Locate and double-click the Silk Test executable file.

If you have a Silk Test CD, insert your CD. If the setup program does not start automatically, manually start the Silk Test setup program by choosing **Start > Run** and entering `<cddrive>:\setup.exe`.



Note: If your Windows *TEMP* environment variable does not point to a valid directory, an error message is displayed. To successfully install Silk Test, your *TEMP* environment variable must point to a valid directory.

The **InstallAnywhere** wizard opens.

2. If a previous version of Silk Test is installed, click **Uninstall** and then click **Next** to remove all installed features.

You must uninstall any earlier versions before you install a new version.

3. Click **Next**. The **License Agreement** opens.
4. Read the license agreement carefully. If you accept the terms of the agreement, click **I accept the terms of the License Agreement**.
5. Click **Next**. The **Choose Install Set** page opens.
6. From the drop-down list, select **Custom** and then check the Silk4NET check box. Silk4NET, Silk Test Recorder, and the Open Agent will be installed.
7. Specify whether you want to install Silk4NET for use with an existing Visual Studio environment.

The Silk4NET Visual Studio plug-in enables you to create VB.NET or C# test scripts directly in Visual Studio.

a) Click one of the following option buttons:

- **Install Silk4NET and use an existing Visual Studio 2010 or later** – To use an existing Visual Studio 2010 or later environment, click this option.
- **Install Silk4NET manually** – To complete the installation of Silk4NET at a later time, click this option. If Visual Studio 2010 or later is not installed on your machine, you must choose this option. Refer to *Installing Silk4NET Visual Studio Plug-in Manually* later in this guide for instructions.

b) Click **Next**.

When you start Visual Studio, a menu option appears for Silk4NET and the Silk4NET project is available from the **Installed Templates** list.

8. To include additional shortcut icons, check one or both of the following check boxes:

- **On the Desktop** – Adds icons to the desktop.
- **In the Quick Launch Bar** – Adds icons to the Quick Launch toolbar.

9. Click **Next**. The **Choose Install Folder** page opens.

10. To change the default installation directory, perform the following steps:

- a) Click **Choose**. The **Browse For Folder** dialog box opens.
- b) Specify the folder in which you want to install Silk Test, and then click **OK** to return to the **Choose Install Folder** page.

The location displays in the **Where Would You Like to Install?** text box.

11. Click **Next**.

12. Specify whether you want to create Windows firewall exceptions.



Note: This step is only available for Windows XP, Windows Vista, Windows 7, and Windows Server 2008.

a) Click one of the following option buttons:

- **Yes** – To have setup create firewall exceptions for all Silk Test executable files. As a result, you are not prompted to block or allow the executable files when you launch them.
- **No** – To be prompted when you launch the Silk Test executable file.

b) Click **Next**.

13. Review the provided information and perform one of the following steps:

- To change any settings, click **Previous** to return to the appropriate page.
- If you are satisfied with the settings, click **Install** to start the installation process.



Tip: If a message appears stating that there is not enough space while files are copying, redefine the TEMP area to a drive that contains more space. The installer uses the TEMP area for unzipping files. For example, if your TEMP area is `d:\temp` and you are installing to `e:\SilkTest`, the E drive may contain enough space for the installation, but the D drive is the limiting factor.

The status bar provides information about the installation process. Upon completion, the **Choose Licensing Mode** page opens.

14. Click one of the following option buttons:

- **Evaluation** Installs an evaluation version of Silk Test, which enables you to explore the full product functionality for 45 days.
- **Full version** – Installs an unrestricted version of Silk Test, which requires a license.

15. The **Select Silk Meter License Server** dialog box opens. This utility checks your local system for the existence of Silk Meter license server configuration files. If the files are found, the configuration and type of license server are displayed and are used for licensing. If no configuration data is found, the **Select SilkMeter License Server** dialog box is displayed with the default settings. Click one of the following option buttons:

Using local or remote server

In the **License Server Host** text box, enter the name of the computer on which Silk Meter is installed. The default **Port**, 5461, should not be changed, unless your network administrator has defined a different port. Click **Test Connection** to verify that a Silk Meter server is accessible on the specified host and port. Testing the connection to the license server may fail during installation as required system libraries, which will be installed later with the software package, may not yet be available.



Note: In some cases, specifying the simple name of the license server in the **License Server Host** text box, such as `licenseserver`, might not work. A message box stating `there is no license server running on the hostname you specified` opens. To resolve this issue, specify the hostname by using a fully qualified name, such as `licenseserver.mycompany.com`.

Using a standalone license

Runs Silk Meter standalone. You are prompted to import a Silk Meter license file. Click **Yes** and specify the location of your license file.



Note: You can import your license file later. Click **Close** to skip this step. The **Select Silk Meter License Server** utility is installed with the product, so that you can access it later from the **Start** menu to test the connection.

16. Click **Next**.



Fastpath: A working network connection is required when running Silk Test with a remote Silk Meter license server. If you need to verify that the network is working, choose **Start > Run**, and then type `ping localhost` or `ping <license server name>`, or open a command prompt and type either of those commands.

17. Click **Done**.

18. Restart Visual Studio if it was running when you performed the Silk4NET installation.

When installation completes, a menu option appears for Silk4NET and the Silk4NET project is available from the **Installed Templates** list.

Installing the Silk4NET Visual Studio Plug-in Manually

The Silk4NET Visual Studio plug-in enables you to create Visual Basic or C# test scripts directly in Visual Studio. You can install the Silk4NET Visual Studio plug-in when you install Silk Test using the Silk Test installation wizard.

Use this procedure:

- If you upgrade your version of Visual Studio after you install the Silk4NET plug-in.
 - If you chose the **Install Silk4NET manually** option during installation.
1. Execute the file `MicroFocus.SilkTest.Silk4NET.vsix` in the folder `<Silk Test installation directory>\ng\Silk4NET`.
By default the location is `C:\Program Files\Silk\Silk Test\ng\Silk4NET`.
 2. In Visual Studio, verify that the menu option for Silk4NET appears and that the Silk4NET project is available from the **Installed Templates** list.

Installing Silk Test Classic

Before you start, download the Silk Test executable file or insert the SilkTest CD into the CD drive.


Silk Test Classic is automatically installed when you choose a complete installation. If you choose a custom installation, you can install Silk Test Classic to use only the traditional 4Test interface and tools. When you install Silk Test Classic, Silk Test Recorder, Silk Test Classic Agent, and the Open Agent are also installed. Silk Test Recorder enables you to record tests rather than manually coding them. Silk Test Classic uses the Classic Agent or the Open Agent to connect to supported technology domains. While the Open Agent is required for the Silk Test Recorder.



Note: If User Account Control (UAC) is activated on your system, we recommend that you install Silk Test Classic into a different location than the `Program Files` folder.

1. Locate and double-click the Silk Test executable file.

If you have a Silk Test CD, insert your CD. If the setup program does not start automatically, manually start the Silk Test setup program by choosing **Start > Run** and entering `<cddrive>:\setup.exe`.

 **Note:** If your Windows *TEMP* environment variable does not point to a valid directory, an error message is displayed. To successfully install Silk Test, your *TEMP* environment variable must point to a valid directory.

The **InstallAnywhere** wizard opens.

2. If a previous version of Silk Test is installed, click **Uninstall** and then click **Next** to remove all installed features.

You must uninstall any earlier versions before you install a new version.

3. Click **Next**. The **License Agreement** opens.

4. Read the license agreement carefully. If you accept the terms of the agreement, click **I accept the terms of the License Agreement**.

5. Click **Next**. The **Choose Install Set** page opens.

6. From the drop-down list, select **Custom** and check the check box for **Silk Test Classic IDE**. When you install Silk Test Classic, Silk Test Recorder, Silk Test Classic Agent, and the Open Agent are also installed.


7. To include additional shortcut icons, check one or both of the following check boxes:


- **On the Desktop** – Adds icons to the desktop.
- **In the Quick Launch Bar** – Adds icons to the Quick Launch toolbar.

8. Click **Next**. The **Choose Install Folder** page opens.

9. To change the default installation directory, perform the following steps:

- a) Click **Choose**. The **Browse For Folder** dialog box opens.
- b) Specify the folder in which you want to install Silk Test, and then click **OK** to return to the **Choose Install Folder** page.


 **Note:** You cannot install Silk Test and Silk Test Runtime on the same machine.

 **Note:** Silk Test must be installed on a local drive. An error message appears if you specify an invalid installation destination.

The location displays in the **Where Would You Like to Install?** text box.

10. Click **Next**.

11. Specify whether you want to create Windows firewall exceptions.

 **Note:** This step is only available for Windows XP, Windows Vista, Windows 7, and Windows Server 2008.


a) Click one of the following option buttons:

- **Yes** – To have setup create firewall exceptions for all Silk Test executable files. As a result, you are not prompted to block or allow the executable files when you launch them.
- **No** – To be prompted when you launch the Silk Test executable file.

b) Click **Next**.

12. Review the provided information and perform one of the following steps:

- To change any settings, click **Previous** to return to the appropriate page.
- If you are satisfied with the settings, click **Install** to start the installation process.

 **Tip:** If a message appears stating that there is not enough space while files are copying, redefine the *TEMP* area to a drive that contains more space. The installer uses the *TEMP* area for unzipping files. For example, if your *TEMP* area is `d:\temp` and you are installing to `e:\SilkTest`, the E drive may contain enough space for the installation, but the D drive is the limiting factor.

The status bar provides information about the installation process. Upon completion, the **Choose Licensing Mode** page opens.

13. Click one of the following option buttons:

- **Evaluation** Installs an evaluation version of Silk Test, which enables you to explore the full product functionality for 45 days.
- **Licensed** – Installs an unrestricted version of Silk Test, which requires a license.

14. Click **Next** to continue. The **Silk Test licensing** dialog box opens.

This dialog box provides generic information about Silk Meter licensing. For detailed information on Silk Meter licensing, click **Open SilkMeter ReadMe**. This opens the Silk Meter documentation in your default browser.



Note: **Open SilkMeter ReadMe** is disabled if the document is not available in the installation source directory. This is usually the case when installing a Silk Test Web package.

Provided that you have already installed a Silk Meter license server on your computer network, or you know which computer on your network will become the Silk Meter license server, or you want to run Silk Meter in standalone mode, you can open the **Select Silk Meter License Server** dialog box by clicking **OK**.

Click **Cancel** to continue the installation without specifying a Silk Meter license server.

15. Click **Next**.



Fastpath: A working network connection is required when running Silk Test with a remote Silk Meter license server. If you need to verify that the network is working, choose **Start > Run**, and then type `ping localhost` or `ping <license server name>`, or open a command prompt and type either of those commands.

16. Specify whether you want to restart the system to complete the installation and then click **Done**.



Attention: You must restart your computer for Silk Test Classic to work properly.

Installing Silk Test Runtime or the Silk Test Agents

The functionality described in this topic applies only for Silk Test Classic.

Before you start, download the Silk Test executable file or insert the SilkTest CD into the CD drive.

Use Silk Test Runtime to execute a set of tests and view the results.

Install the Silk Test Agent software on machines that are used for distributed testing.

1. Locate and double-click the Silk Test executable file.

If you have a Silk Test CD, insert your CD. If the setup program does not start automatically, manually start the Silk Test setup program by choosing **Start > Run** and entering `<cddrive>:\setup.exe`.



Note: If your Windows *TEMP* environment variable does not point to a valid directory, an error message is displayed. To successfully install Silk Test, your *TEMP* environment variable must point to a valid directory.

The **InstallAnywhere** wizard opens.

2. If a previous version of Silk Test is installed, click **Uninstall** and then click **Next** to remove all installed features.

You must uninstall any earlier versions before you install a new version.


3. Click **Next**. The **License Agreement** opens.

4. Read the license agreement carefully. If you accept the terms of the agreement, click **I accept the terms of the License Agreement**.

5. Click **Next**. The **Choose Install Set** page opens.

6. From the drop-down list, select **Agent/Runtime Only** and check the check boxes for the components that you want to install.


- Check the **Open Agent** check box to perform distributed testing on tests in Silk4J, Silk Test Workbench, Silk Test Recorder, Silk4NET, and most of the technology types for Silk Test Classic.
- Check the **Silk Test Classic Agent** check box to perform distributed testing in a traditional 4Test environment. The Silk Test Classic Agent software includes the Silk Test Unix Agent.
- Check the **Silk Test Classic Runtime** check box to execute a set of tests and view the results.


 **Note:** The Agent installation includes the Silk Test Windows and .NET extension kits, which are included as part of the Silk Test Classic Agent installation.

7. Click **Next**. The **Choose Install Folder** page opens.

8. To change the default installation directory, perform the following steps:


- a) Click **Choose**. The **Browse For Folder** dialog box opens.
- b) Specify the folder in which you want to install Silk Test, and then click **OK** to return to the **Choose Install Folder** page.

 **Note:** You cannot install Silk Test and Silk Test Runtime on the same machine.

 **Note:** Silk Test must be installed on a local drive. An error message appears if you specify an invalid installation destination.

9. Click **Next**. The **Firewall Exceptions** page opens.

10. Specify whether you want to create Windows firewall exceptions.

 **Note:** This step is only available for Windows XP, Windows Vista, Windows 7, and Windows Server 2008.


a) Click one of the following option buttons:

- **Yes** – To have setup create firewall exceptions for all Silk Test executable files. As a result, you are not prompted to block or allow the executable files when you launch them.
- **No** – To be prompted when you launch the Silk Test executable file.

b) Click **Next**.

11. Review the provided information and perform one of the following steps:

- To change any settings, click **Previous** to return to the appropriate page.
- If you are satisfied with the settings, click **Install** to start the installation process.

 **Tip:** If a message appears stating that there is not enough space while files are copying, redefine the TEMP area to a drive that contains more space. The installer uses the TEMP area for unzipping files. For example, if your TEMP area is d:\temp and you are installing to e:\SilkTest, the E drive may contain enough space for the installation, but the D drive is the limiting factor.

The status bar provides information about the installation process. Upon completion, the **Choose Licensing Mode** page opens.

12. Click one of the following option buttons:

- **Evaluation** Installs an evaluation version of Silk Test, which enables you to explore the full product functionality for 45 days.
- **Licensed** – Installs an unrestricted version of Silk Test, which requires a license.

13. The **Select Silk Meter License Server** dialog box opens. This utility checks your local system for the existence of Silk Meter license server configuration files. If the files are found, the configuration and type of license server are displayed and are used for licensing. If no configuration data is found, the **Select SilkMeter License Server** dialog box is displayed with the default settings. Click one of the following option buttons:

| | |
|-------------------------------------|--|
| Using local or remote server | In the License Server Host text box, enter the name of the computer on which Silk Meter is installed. The default Port , 5461, should not be changed, unless your network administrator has defined a different port. Click Test Connection to verify |
|-------------------------------------|--|

that a Silk Meter server is accessible on the specified host and port. Testing the connection to the license server may fail during installation as required system libraries, which will be installed later with the software package, may not yet be available.



Note: In some cases, specifying the simple name of the license server in the **License Server Host** text box, such as `licenseserver`, might not work. A message box stating there is no license server running on the hostname you specified opens. To resolve this issue, specify the hostname by using a fully qualified name, such as `licenseserver.mycompany.com`.

Using a standalone license

Runs Silk Meter standalone. You are prompted to import a Silk Meter license file. Click **Yes** and specify the location of your license file.



Note: You can import your license file later. Click **Close** to skip this step. The **Select Silk Meter License Server** utility is installed with the product, so that you can access it later from the **Start** menu to test the connection.

14. Click **Next**.



Fastpath: A working network connection is required when running Silk Test with a remote Silk Meter license server. If you need to verify that the network is working, choose **Start > Run**, and then type `ping localhost` or `ping <license server name>`, or open a command prompt and type either of those commands.

15. Specify whether you want to restart the system to complete the installation and then click **Done**.



Attention: You must restart your computer for Silk Test Classic to work properly.



Note: If you purchase a license for a Silk Test Agent but not Silk Test itself, then only the Agent, documentation and the Silk Test Bitmap Tool are accessible after you install Silk Test.

Installing the Classic Agent for Unix

After you install the Silk Test Agent software, additional steps are required if you want to use the Silk Test Classic Agent for Unix.

1. On the computer where you installed the Silk Test Classic Agent software, locate the directory where the Silk Test Unix Agent TAR files are.

By default, this location is `c:\Program Files\Silk\Silk Test\unix_agent`.

2. Copy the TAR file that is appropriate for your Unix machine.

Silk Test provides the following files:

- `linux21_sp3.tar.gz` – For Linux 2.1
- `linux30_sp3.tar.gz` – For Linux 3.0
- `solaris_sp3.tar.gz` – For Solaris 9 and 10

3. Extract the TAR file on your Unix machine by typing `tar xzf <filename>.tar.gz`.

where `<filename>` is the appropriate file name for your version of Unix.

4. Change to the `bin` directory and then run a shell or `cshell` script.

For instance, type:

```
cd bin
csh <filename>
```

5. Start the Agent.

Uninstalling Silk Test

When you install a new version of Silk Test, the wizard prompts you to uninstall any existing versions of Silk Test. You can also uninstall Silk Test from the programs menu at any time.

1. Click **Start > Programs > Silk > Silk Test > Administration > Silk Test Uninstall**. The **InstallAnywhere** wizard opens the **Uninstall Silk Test <version>** page.

2. To remove all files from the installation directory, check the **Remove all files** check box.

If you check this check box, the following items or folders are removed:

- The Access database and samples
- The contents of [AppDATA]/Silk/Silk Test

For example, on Windows 7 this directory is located at: C:\Users\[username]\AppData\Roaming\Silk\Silk Test

- The contents of [commonAppData]/Silk/Silk Test

For example, on Windows 7 this directory is located at: C:\ProgramData\Silk Test

- The contents of [commonAppData]/Silk/Silk Test Workbench

For example, on Windows 7 this directory is located at: C:\ProgramData\Silk Test Workbench

3. Click **Uninstall**. If any files were not removed, a list of the files is provided.

4. Click **Done**.

Silk Test Silent Mode Installation

During a typical user-driven installation, the install process gets its information from a user responding to dialog boxes. However, during a silent installation, the installation process gets its information from a properties file. Silent installation is especially useful if you want to distribute software over a LAN or the Internet by using remote installation tools. You can execute silent installs of the following types:

- Complete – Installs Silk Test Workbench, the Silk Test Agents, Silk Test Recorder, Silk4J, Silk4NET, and Silk Test Classic.
- Standard – Installs Silk Test Workbench, the Silk Test Open Agent, Silk Test Recorder, Silk4J, and Silk4NET.
- Basic – Installs Silk Test Workbench and the Silk Test Open Agent.
- Agent/Runtime – Installs Silk Test Runtime and the Silk Test Agents.

Creating a Silent Installation Properties File

Before you can run the installation package in silent mode, you must create a properties file that includes the settings for the installation.

1. Open a text editor, such as Notepad.

2. Paste the following example into the text editor, name the file, and then save the file with a `.properties` extension.

For example, you might call the file `SilentInstall.properties`.

```
# Silent Installation Execution Instructions:
#####
# Start the Install.exe (not Setup.exe) with the following arguments:
# -i silent -f [path to properties file][properties file]
# (You may use the direct or the relative path to the properties file)
```

```

#
# example: install.exe -i silent -f SilentInstall.properties
#
# SilkTest installation path - use "\\" to separate directories
# (default: [System_Programs_Folder]\\Silk\\Silk Test)
#####
# USER_INSTALL_DIR=C:\\Program Files\\Silk\\Silk Test
#
# Select an install set:
# (default: 1)
#####
# 0 - Basic (Workbench)
# 1 - Standard (Workbench, Silk4J, Silk4NET)
# 2 - Complete
# 3 - Agent/Runtime Only
# NONE - Custom mode
# SELECTED_INSTALL_SET=1
#
# Shortcut locations: enter the location(s) for icons.
# (allowed: Desktop, QuickLaunch)
# (default: no shortcuts)
#####
# SHORTCUT_LOCATIONS=Desktop,QuickLaunch
#
# Path to the existing Eclipse directory (containing eclipse.exe) into
# which Silk4J will be integrated
# (default: USER_INSTALL_DIR)
#####
# ECLIPSE_CHOSEN_DIR=C:\\Eclipse
#
# Silk4NET installation option: if set to 1, Silk4NET will be integrated
# into an existing VS2010
# (default: 0)
#####
# USER_INPUT_SILK4NET_INTEGRATE=1
#
# Start notification service: If set to 1, the
# SilkTest Product Notification Service is started.
# The service displays the currently installed SilkTest version
# and the most recent version that is available for you
# to download.
# (default: 1)
#####
# START_NOTIFICATION_SERVICE=0
#
# Firewall exceptions:
# (default: no exceptions)
#####
# USER_INPUT_FIREWALL=Yes
#
# Create system restore point
# (default: 1)
#####
# CREATE_SYSTEM_RESTORE=0
#
# Licensing Mode (no default value)
#####
# Use to install an evaluation license
# USER_VERSION_EVAL=1
#
# Use to install a full license
# USER_VERSION_FULL=1
#
# Settings that specify the license server and port

```



```
# (no default values)
#####
# LICENSE_SERVER=localhost
# Port of license server
# LICENSE_PORT=5461
```

Setting Up the Silent Installer

Before you can set up the properties for the silent installer, you must create a properties file that includes the settings for the installation.



Note: To set a property value, make sure to remove the hash (#) sign from the property value string.

1. In a text editor, open the properties file that you created for the silent installation.
2. Locate the `SELECTED_INSTALL_SET` property and set the value to match the type of installation that you want to complete.

Choices include:

```
# 0 - Basic (Workbench)
# 1 - Standard (Workbench, Silk4J, Silk4NET)
# 2 - Complete
# 3 - Agent/Runtime Only
# NONE - Custom mode
```

For example:

- To install the complete version of Silk Test, type:

```
SELECTED_INSTALL_SET=2
```

- To install Silk Test Classic, type:

```
SELECTED_INSTALL_SET=NONE
CHOSEN_INSTALL_FEATURE_LIST=OA,CA,Partner
```



Note: When you use the custom mode, you can specify the components that you want to install by setting the `CHOSEN_INSTALL_FEATURE_LIST`. Do not set this option if you use another mode. The list includes the following components:

| Component | Value |
|---------------------|----------|
| Open Agent | OA |
| Silk Test Workbench | VT |
| Classic Agent | CA |
| Silk Test Classic | Partner |
| Silk4J | Silk4J |
| Silk4NET | Silk4NET |
| Silk Test Runtime | RunTime |

3. To include additional shortcut icons, locate the `SHORTCUT_LOCATIONS` property and specify one or both of the following options:
 - **Desktop** – Adds icons to the desktop.
 - **QuickLaunch** – Adds icons to the Quick Launch toolbar.

For example to install both the Desktop and Quick Launch icons, type:

```
SHORTCUT_LOCATIONS=Desktop,QuickLaunch
```

4. To integrate an existing Eclipse environment with the Silk4J Java Testing Framework (JTF), locate the `ECLIPSE_CHOSEN_DIR` property and specify the Eclipse directory location.

For example, you might specify:

```
ECLIPSE_CHOSEN_DIR=C:\\Eclipse
```

where `C:\\Eclipse` is the directory where Eclipse is installed.



Note: Directory levels are specified with a double `\\`.

5. To install Silk4NET for use with an existing Visual Studio environment, locate the `USER_INPUT_SILK4NET_INTEGRATE` property and specify one of the following options:

- 0 – Silk4NET is not set up for use.
- 1 – Silk4NET is set up for use.

The Silk4NET Visual Studio plug-in enables you to create VB.NET or C# test scripts directly in Visual Studio.

For example, you might specify:

```
USER_INPUT_SILK4NET_INTEGRATE=1
```

6. To specify the language for the Classic Agent browser application, locate the `USER_INPUT_BROWSER_LANGUAGE` property and specify one of the following languages:

By default, English is specified.

- English
- Simplified Chinese
- French
- German
- Japanese

For example, you might specify:

```
USER_INPUT_BROWSER_LANGUAGE=English
```

7. To specify the default browser for the Classic Agent, locate the `USER_INPUT_DEFAULT_BROWSER` property and specify one of the following choices:

By default, the installer uses the default system browser, if it supported by Silk Test.

- None - Choose None if you do not test with the Classic Agent or if you do not test web applications.
- Firefox
- Internet Explorer

For example, you might specify:

```
USER_INPUT_DEFAULT_BROWSER=Firefox
```

8. To specify the Internet Explorer version for the Classic Agent, locate the `IE_VERSION` property and specify 6, 7, or 8.

For example, you might specify:

```
IE_VERSION=7
```

9. To specify the FireFox version for the Classic Agent, locate the `FIREFOX_DOMEX_VERSION` property and specify 1_5 or 2_0.

For example, you might specify:

```
FIREFOX_DOMEX_VERSION=2_0
```

10. Specify whether the installation includes Windows firewall exceptions for all Silk Test executable files.



Note: This step is only available for Windows XP, Windows Vista, Windows 7, and Windows Server 2008.

By default, no firewall exceptions are set.

For example, to create Windows firewall exceptions specify:

```
USER_INPUT_FIREWALL=Yes
```

11. Specify whether the installation requires an evaluation license or a full license.

- To use a 45-day trial evaluation license, type:

```
USER_VERSION_EVAL=1
```

- To use a full license, type:

```
USER_VERSION_FULL=1
```

12. To specify the license server name, locate the `LICENSE_SERVER` property and specify the server name.

This value is not set by default. To use your local machine, in most cases, you type `localhost`.

13. To specify the license server port, locate the `LICENSE_PORT` section.

This value is not set by default. To use the predefined port, type `5461`.

14. Save the file.


Run the silent installation command to launch the installation.

Using the Web Installer to Install in Silent Mode

Before you can run the installation package in silent mode, you must

- Create a properties file that includes the settings for the installation.
- Install Windows Installer version 4.5 on the host machine.

When you use the **Installation** wizard, Windows Installer version 4.5 is installed automatically. When you use Silent mode, you must manually install this component if it is not already on the machine.


 **Caution:** Ensure that earlier versions of Silk Test have been uninstalled before proceeding. If an earlier version of Silk Test is located on the computer, Silk Test overwrites the existing files without notification. Do not install multiple versions of Silk Test on the same machine.

To install Silk Test with the Web installer and without any user interaction:

1. Locate the installation package on your hard drive.
2. To execute silent installation, enter the following command from a DOS shell or batch file.

```
SilkTest<Version>.exe -i silent -f [path to properties file]\[properties file]
```

Where the `<Version>` is the Silk Test version and build number, for example `SilkTest14.0_6393.exe`

 **Note:** The properties file is a text file with the extension `.properties`. You can name the file whatever you choose.

For example, if the silent installation properties file is located in the same directory as the `SilkTest<Version>.exe`, you might specify:

```
SilkTest<Version>.exe -i silent -f SilentInstall.properties
```

If the `SilkTest<Version>.exe` is not located in the same directory as the silent installation properties file, specify the absolute path to the properties file location. For example:

```
SilkTest<Version>.exe -i silent -f C:\temp\SilentInstall.properties
```

Silk Meter is a licensing tool; when you run the silent installer it “skips” detecting a Silk Meter server. If you have not already configured your license server, you may have to do so after you install Silk Test with the silent installer.

Using the Installation CD to Install in Silent Mode

Before you can run the installation package in silent mode, you must

- Create a properties file that includes the settings for the installation.
- Install Windows Installer version 4.5 on the host machine.

When you use the **Installation** wizard, Windows Installer version 4.5 is installed automatically. When you use Silent mode, you must manually install this component if it is not already on the machine.



Caution: Ensure that earlier versions of Silk Test have been uninstalled before proceeding. If an earlier version of Silk Test is located on the computer, Silk Test overwrites the existing files without notification. Do not install multiple versions of Silk Test on the same machine.

To install Silk Test from the installation CD without any user interaction:

1. Copy the contents of the Silk Test installation CD to an empty directory on your hard drive.
2. To execute silent installation, enter the following command from a DOS shell or batch file.

```
SilkTest<Version>.exe -i silent -f [path to properties file]\[properties file]
```

Where the *<Version>* is the Silk Test version and build number, for example `SilkTest14.0_6393.exe`



Note: The properties file is a text file with the extension `.properties`. You can name the file whatever you choose.

For example, if the silent installation properties file is located in the same directory as the `SilkTest<Version>.exe`, you might specify:

```
SilkTest<Version>.exe -i silent -f SilentInstall.properties
```

If the `SilkTest<Version>.exe` is not located in the same directory as the silent installation properties file, specify the absolute path to the properties file location. For example:

```
SilkTest<Version>.exe -i silent -f C:\temp\SilentInstall.properties
```

Silk Meter is a licensing tool; when you run the silent installer it “skips” detecting a Silk Meter server. If you have not already configured your license server, you may have to do so after you install Silk Test with the silent installer.

Verifying the Success of the Silent Installer

When you run the Silent Installer, you may not see any messages or Silk Test dialog boxes. It may be difficult to know whether the installation was a success. You can, however, review the `SilkTest_<version>_InstallLog.log` file, which contains the status of the install. By default, the `SilkTest_<version>_InstallLog.log` file is generated in the Silk Test installation directory. We recommend examining the log file before you make the Silent Installer available for others to use.



Note: If an earlier version of Silk Test, such as Silk Test 2009, is detected on the computer, Silk Test continues the installation and does not include an entry in the log file. Do not install multiple versions of Silk Test on the same machine.

1. Locate the `SilkTest_<version>_InstallLog.log` file and open it in a text editor.
2. To determine whether the Silent Installer succeeded, review the status messages for each action performed by the setup.

The installation log records `SUCCESSFUL`, `WARNING`, or `ERROR` for each action the installer executes. The installation log also includes a summary which tallies the number of successes, warnings, non-fatal errors, or errors.

For example, an action might look like the following:

```
Install File: C:\Program Files\Silk\Silk Test\ng\recorder\plugins\
              com.borland.silktest.recorder_11.1.0.4440\plugin.xml
Status: SUCCESSFUL
```

The summary might look like the following:

```
Summary
```

```
-----
```

```
Installation: Successful.
```

```
2497 Successes
```

```
0 Warnings
```

```
0 NonFatalErrors
```

```
0 FatalErrors
```

Viewing Error Codes

View the installation error codes to analyze the errors that occurred during silent installation.

1. Create a batch file to start the installation and run it.

For example, you might create a file named `install.bat` with the following code:

```
@echo off
install.exe -I silent -f SilentInstall.properties
echo %errorlevel%
pause
```

2. Review the installation codes.

The following table lists possible return values for the `Code` keyname.

Table 1: Installer Exit Codes

| Code | Description |
|------|--|
| 0 | Success: The installation completed successfully without any warnings or errors. |
| 1 | The installation completed successfully, but one or more of the actions from the installation sequence caused a warning or a non-fatal error. |
| -1 | One or more of the actions from the installation sequence caused a fatal error. |
| 1000 | The installation was cancelled by the user. |
| 1001 | The installation includes an invalid command line option. |
| 2000 | Unhandled error. |
| 2001 | The installation failed the authorization check, may indicate an expired version. |
| 2002 | The installation failed a rules check. A rule placed on the installer itself failed. |
| 2003 | An unresolved dependency in silent mode caused the installer to exit. |
| 2004 | The installation failed because not enough disk space was detected during the execution of the Install action. |
| 2005 | The installation failed while trying to install on a Windows 64-bit system, but installation did not include support for Windows 64-bit systems. |
| 2006 | The installation failed because it was launched in a UI mode that is not supported by this installer. |
| 3000 | Unhandled error specific to a launcher. |
| 3001 | The installation failed due to an error specific to the <code>lax.main.class</code> property. |
| 3002 | The installation failed due to an error specific to the <code>lax.main.method</code> property. |
| 3003 | The installation was unable to access the method specified in the <code>lax.main.method</code> property. |
| 3004 | The installation failed due to an exception error caused by the <code>lax.main.method</code> property. |
| 3005 | The installation failed because no value was assigned to the <code>lax.application.name</code> property. |

| Code | Description |
|------|---|
| 3006 | The installation was unable to access the value assigned to the <code>lax.nl.java.launcher.main.class</code> property. |
| 3007 | The installation failed due to an error specific to the <code>lax.nl.java.launcher.main.class</code> property. |
| 3008 | The installation failed due to an error specific to the <code>lax.nl.java.launcher.main.method</code> property. |
| 3009 | The installation was unable to access the method specified in the <code>lax.nl.launcher.java.main.method</code> property. |
| 4000 | A Java executable could not be found at the directory specified by the <code>java.home</code> system property. |
| 4001 | An incorrect path to the installer jar caused the relauncher to launch incorrectly. |

Uninstalling in Silent Mode

Uninstall in silent mode to uninstall Silk Test without any user interaction.



Note: You can uninstall Silk Test with silent mode regardless of how you installed the product. However, if you install Silk Test in silent mode, the uninstall mode is executed silently also.

1. Locate the `Uninstall_Silk Test <version>` folder.

The `Uninstall_Silk Test <version>.exe` is located in this folder.

2. To execute the silent mode uninstallation procedure, enter one of the following commands from a DOS shell or batch file.

- If you installed Silk Test in silent mode, enter the following command.

```
<Silk Test Install Directory>\Silk\Silk Test\Uninstall_Silk Test
2011\Uninstall_Silk <version>.exe
```

- If you did not install Silk Test in silent mode, enter the following command.

```
<Silk Test Install Directory>\Silk\Silk Test\Uninstall_Silk Test <version>
\Uninstall_Silk Test <version>.exe -I silent
```

For example, you might type the following command if you did not install Silk Test in silent mode:

```
C:\Program Files\Silk\Silk Test\Uninstall_Silk Test <version>\Uninstall
Silk Test <version>.exe -I silent
```

What To Do Next

Try the tutorials

If you are new to Silk Test, we recommend that you try the Silk Test tutorials, available from **Start > Programs > Silk > Silk Test > Documentation > Tutorials**.

Configuring a Silk Test Workbench Database



Note: If a database update was required to install a new version of Silk Test Workbench, all Silk Test Workbench users need to update to the new version of the database.

This section contains topics describing how to configure a Silk Test Workbench database.

Configuring an SQL Server Database Overview



Important: We recommend that a database administrator or person with general knowledge of database administration performs the database setup and configuration.

Silk Test Workbench stores and accesses test assets stored in a database configured for use with Silk Test Workbench. This section describes how to configure the following SQL Server databases to use as a Silk Test Workbench database.

For information about new features, supported platforms and versions, known issues, and work-arounds, refer to the [Release Notes](#).

SQL Server Requirements

A SQL Server database configured for use with Silk Test Workbench has the following requirements:

- Each computer running Silk Test Workbench must be able to access the computer where the SQL Server database resides and have a new data source configured.
- Silk Test Workbench must be installed on all computers accessing the database.
- The Silk Test Workbench database connection file must be configured to point to the SQL Server database.



Note: Silk Test cannot use 64-bit DSNs. You can review the default DSNs and ODBC drivers for 64-bit machines using the WOW64 tools, which are located at `C:\Windows\SysWow64`.

For additional information about maintaining a Silk Test Workbench database, refer to the *Silk Test Workbench Help*.

Creating a New SQL Server Database

This section describes how to create a SQL Server database using SQL Server Management Studio. In addition to the following procedures, you must also populate the database with Silk Test Workbench tables using the Silk Test Workbench Database Maintenance utility.

1. In the Object Explorer of SQL Server Management Studio, right-click the **Databases** folder and choose **New Database**. The **New Database** dialog box opens.
2. Enter a name for the database in the **Database name** text box.
3. Click **OK**.

Creating a New SQL Server Admin User

A SQL Server user with system administrator rights is required to perform subsequent setup steps.

1. To create a new user with system administrator rights, perform the following steps:

- a) In the Object Explorer of SQL Server Management Studio, navigate to the **Security** folder and expand it.
 - b) Right-click the **Logins** folder and choose **New Login**. The **Login - New** dialog box opens.
 - c) Select the **General** page, and then enter a user name in the **Login name** text box.
 - d) Select SQL Server Authentication and enter a password.
 - e) Select the default database from the **Default database** list.
 - f) Select the **Server Roles** page, and then check the **sysadmin** check box in the **Server roles** list.
 - g) Select the **User Mapping** page.
 - h) In the **Map** column, check the check box for the database that the new login can access.
By default, the login name appears in the **User** column. Leave this value.
 - i) In the **Database role membership for** list, check the **db_owner** check box.
 - j) Click **OK**.
2. To create a new schema for the new user, perform the following steps:
- a) In the **Object Explorer**, navigate to the database in which you want to create a schema.
 - b) Expand the database object tree to show the **Schemas** folder.
The **Schemas** folder is a child of the **Security** folder for the database.
For example, if you are adding a schema to the *master* database, expand the following folders to show the **Schemas** folder: **Databases > System Databases > master > Security**.
 - c) Right-click the **Schemas** folder and choose **New Schema**.
 - d) In the **Schema name** text box, type a name for the new schema.
The new schema name must match the name of the previously created user with system admin rights.
 - e) Assign the new user with system administrator rights as the owner of the schema.
 - f) Click **OK**.
3. Select the newly created user and set the default schema to the newly created schema.

Setting Up Users in SQL Server


The following procedure should be performed on the database server computer for each user who needs to connect to the SQL server database.


1. In the Object Explorer of SQL Server Management Studio, navigate to the **Security** folder and expand it. Right-click the **Logins** folder and choose **New Login**. The **Login - New** dialog box opens.
2. Select the **General** page, and then enter a name for the database in the **Login name** text box.
3. Select either **Windows Authentication** or **SQL Server Authentication**.
4. Select the default database from the **Default database** list.
5. Select the **User Mapping** page.
6. In the **Map** column, check the check box for the database that your login can access.
By default, the login name appears in the **User** column. Leave this value.
7. In the **Default Schema** column, enter the default schema.
For use with Silk Test Workbench, the default schema must match the schema of the previously created user with system admin rights.
8. In the **Database role membership for** list, leave the default option **public** selected.
9. Check the **db_datareader** and **db_datawriter** check boxes.
10. Click **OK**.



Important: To use SQL Server Express with multiple users, each SQL Server Express installation must be enabled for remote connectivity. To enable SQL Server Express for remote connectivity, refer to the Microsoft support article *How to enable remote connections on SQL Server*.


Preparing the SQL Server Silk Test Workbench Database

 **Note:** SQL Server Authentication Mode must be set to: SQL Server and Windows (Mixed Mode) to allow connection to the SQL Server database through the Database Maintenance utility. This setting can be changed after any database maintenance tasks are performed.

 **Note:** You can only perform the tasks described in this topic if the SQL Server database is empty.

You must prepare your new SQL Server database for use with Silk Test Workbench. This section describes how to use the Database Maintenance utility to populate the database with Silk Test Workbench tables.


1. Click **Start > Programs > Silk > Silk Test > Administration > Database Maintenance**. The **Database Maintenance** utility starts.
2. Click **File > New Database > SQL Server**. The **SQL Server Data Source Connection** dialog box opens.
3. Type the name of the new SQL Server data source or click **Browse** and select a data source name from the **Select ODBC Data Source** dialog box.
4. In the appropriate text boxes, type the name of the database owner, which is the user with the role db_owner, and the SQL Server user ID and password, and then click **Create**.

 **Note:** Only one schema can be associated with a DSN name (ODBC connection). If the chosen DSN name is already associated with a schema, click **Replace** to change the association of the DSN name from its current schema to the new schema (users will no longer be able to access Silk Test Workbench tables in the old schema), or click **Alias** to create an alias for the DSN name.

You are now ready to start Silk Test Workbench and log on.

Configuring an Oracle Database Overview

This section describes how to set up an Oracle database with Silk Test Workbench.

 **Note:** The following instructions assume familiarity with the Oracle database management system. We recommend that a database administrator or a person with general knowledge of database administration performs database setup and configuration.

Each client computer requires an ODBC data source to connect to the database. As a result, connecting to an Oracle database for Silk Test Workbench has the following requirements:

- Each computer running Silk Test Workbench must be able to access the computer where the database resides and have a new data source configured.
- Silk Test Workbench must be installed on all computers that access the database.
- The appropriate database client connectivity software must be installed on any computer that runs Silk Test Workbench.
- The database connection must be configured for use with Silk Test Workbench.

Selecting an Authentication Method

Silk Test Workbench supports the use of either Oracle OS authentication (Windows NT) or Oracle database authentication. There are additional installation procedures required when using Oracle OS authentication.

Oracle OS Authentication

This topic provides instructions for creating users and granting connection rights when using Oracle OS authentication. Prior to performing these steps, consider the following:

- You must be a member of the `ORA_DBA` group and have `SYSDBA` privileges.
- Users must be created in such a way that Oracle knows they are authenticated via a `DOMAIN` controller.
- Use `SQL*Plus` or `SQL*Plus Worksheet` to create users. If you are not familiar with `SQL*Plus`, consult your Oracle documentation.
- Users must be created within a Windows NT domain and added to the `ORA_DBA` group. Refer to your Microsoft Windows documentation for more information about using a Windows domain.
- When setting up users for Silk Test Workbench in Oracle, create a schema to house the actual tables in addition to the remotely authenticated users. The schema is not domain authenticated, but is password authenticated.

1. Start `SQL*Plus` or `SQL*Plus Worksheet`.

2. Log on as `SYSTEM` and connect as `SYSDBA`.

3. Type commands to create each user as `"DOMAIN\USERNAME" IDENTIFIED EXTERNALLY`, and grant connection rights and system privileges as shown in the following example.

For each user as `"DOMAIN\USERNAME"`. Type `DOMAIN\USERNAME` in uppercase and between double quotation marks, where `DOMAIN\USERNAME` is each user's domain and user name.

For example:

```
CREATE USER "NT-DOMAIN\JEFF" IDENTIFIED EXTERNALLY;  
GRANT SELECT ANY SEQUENCE TO "NT-DOMAIN\JEFF";  
GRANT UNLIMITED TABLESPACE TO "NT-DOMAIN\JEFF";  
GRANT "CONNECT" TO "NT-DOMAIN\JEFF";  
GRANT "RESOURCE" TO "NT-DOMAIN\JEFF";  
GRANT "SELECT_CATALOG_ROLE" TO "NT-DOMAIN\JEFF";
```



Important: Microsoft operating systems return the `DOMAIN\USERNAME` when the user is queried. If this does not match what is defined in the database, Oracle OS authentication will fail with `ORA-1017`.

4. Test that Oracle OS authentication is set up correctly by connecting to the database via `SQL*Plus`.

a) Type a `"/` for the user name.

b) Leave the Password text box empty, and enter the host string appropriately.

c) Click **OK**. If you can log on, Oracle OS authentication is working properly.

Oracle Database Authentication

This topic provides instructions for creating users and granting connection rights when using Oracle database authentication. Prior to performing these steps, consider the following:

- You must be a member of the `ORA_DBA` group and have `SYSDBA` privileges.
- Users must be created in such a way that Oracle knows they are authenticated via a `DOMAIN` controller.
- Use `SQL*Plus` or `SQL*Plus Worksheet` to create users. If you are not familiar with `SQL*Plus`, consult your Oracle documentation.
- Users must be created within a Windows NT domain and added to the `ORA_DBA` group. Refer to your Microsoft Windows documentation for more information about using a Windows domain.
- When setting up users for Silk Test Workbench in Oracle, create a schema to house the actual tables in addition to the remotely authenticated users. The schema is not domain authenticated, but is password authenticated.

1. Start SQL*Plus or SQL*Plus Worksheet.
2. Log on as SYSTEM and connect as SYSDBA.
3. Type commands to create each user as "USERNAME" IDENTIFIED BY "ORACLEPASSWORD", and grant connection rights and system privileges as shown in the following example.

For each user as "USERNAME". Type USERNAME in uppercase and between double quotation marks, where DOMAIN\USERNAME is each user's user name.

For example:

```
CREATE USER "JEFF" IDENTIFIED BY "ORACLEPASSWORD" ;
GRANT SELECT ANY SEQUENCE TO "JEFF" ;
GRANT UNLIMITED TABLESPACE TO "JEFF" ;
GRANT "CONNECT" TO "JEFF" ;
GRANT "RESOURCE" TO "JEFF" ;
GRANT "SELECT_CATALOG_ROLE" TO "JEFF" ;
```

Creating a New Oracle Database

Create a new Oracle database with character set UTF8. For more information, refer to the Oracle product documentation.

Setting Up Oracle Authentication



Note: This procedure is only necessary if you use Oracle OS authentication. If you use Oracle database authentication, you must set up the Oracle client.

1. On the server where the database is located, locate the Oracle Initialization file in the directory where Oracle was installed.
2. In the Oracle Initialization file, set values for the following parameters:
 - remote_login_passwordfile = none
 - remote_os_authent = true
 - os_authent_prefix = ""



Note: If any of the parameters and values do not exist, you must add them. In Oracle 11g, the remote_os_authent and os_authent_prefix parameters are set by default.

3. Locate the SQLNET.ORA file in the directory where Oracle was installed.

The file is located in ORACLE_HOME\Network\Admin directory under the main Oracle installation directory where ORACLE_HOME is the name assigned for the Oracle home during installation.

4. Open SQLNET.ORA and set the value of the following parameter as follows:

```
sqlnet.authentication_services = (NTS)
```



Note: Ensure this parameter is not commented out with a # at the beginning of the line. You may need to add this parameter.

5. Access the **Run** dialog box from the **Start** menu.
6. In the **Open** text box, type regedit and then click **OK**. The **Registry Editor** dialog box opens.
7. In the path HKEY_LOCAL_MACHINE\SOFTWARE\ORACLE\HOMEn (where n is the number associated with the Oracle installation), right-click HOMEn and choose **New > String Value**. A new string value appears in the right pane of the registry editor.
8. Replace the default name, New Value #1 with OSAUTH_PREFIX_DOMAIN.
9. Double-click the string value you just created. The **Edit String** dialog box opens.
10. In the **Value data** text box, type TRUE and then click **OK**.

Setting Up the Oracle Client

On the client computer from which you will connect:

1. Locate the `SQLNET.ORA` file in the directory where Oracle was installed.

The file is located in `ORACLE_HOME\Network\Admin` directory under the main Oracle installation directory where `ORACLE_HOME` is the name assigned for the Oracle home during installation.

2. Open `SQLNET.ORA` and set the value of the following parameter as follows:

```
sqlnet.authentication_services = (NTS)
```



Note: Ensure this parameter is not commented out with a `#` at the beginning of the line. You may need to add this parameter.

3. Open the `TNSNAMES.ORA` file in the directory where Oracle was installed.

This file is located in `ORACLE_HOME\Network\Admin` directory.

4. Copy the server's database entry to the `TNSNAMES.ORA` file on the client computer.
For example:

```
ORACLE_SID.DOMAIN.COM=  
(DESCRIPTION=  
(ADDRESS_LIST=  
(ADDRESS=(PROTOCOL=TCP)(HOST=SERVERNAME)(PORT=1521))  
)  
(CONNECT_DATA=  
(SERVICE_NAME=ORACLE_SID)  
)  
)
```

Preparing the Oracle Database for Client Connectivity



Note: This procedure is only necessary if you are using Oracle OS authentication and an Oracle client to set up the Silk Test Workbench database. If you are using Oracle database authentication, you can begin to set up users.

1. On the computer that has User Manager for Domains, access the Windows **Control Panel**, and then choose **Administrative Tools > Computer Management**

The **Computer Management** utility opens.

2. In the tree view, click **Local Users and Groups**.
3. Click **Groups**.

If Oracle is installed, you should see a group named `ORA_DBA`. If not, you must add it.

Next, create server access for users.

Creating the ORA_DBA Group

1. In the tree view of the **Computer Management** utility, right-click **Groups** and choose **New Group**. The **New Group** dialog box opens.
2. In the **Group Name** text box, type `ORA_DBA`.
3. Click **Create**.
4. Click **Close**.

Creating Server Access for Users

To create individual user accounts:

1. In the tree view of the **Computer Management** utility, click **Local Users and Groups**.
2. Click **Groups**.
3. In the right pane, double-click **ORA_DBA**. The **ORA_DBA Properties** dialog box opens.
4. Click **Add**. The **Select Users, Computers, or Groups** dialog box opens.
5. Click **Advanced**, then use the **Common Queries** tab to search for users, click **Find Now** and select users from the list.

Alternatively, click in the **Enter the object names to select** text box and type the following: `domain name\user ID`

Where `domain name` is the name of the domain where the user is located and `user ID` is the network ID of the user you want to give access to.

6. Click **OK** to save the user information and return to the **ORA_DBA Properties** dialog box.
Repeat steps 4–6 to create any additional user accounts.
7. Click **OK** in the **Users Properties** dialog box to return to the **Computer Management** utility.

Setting Up Users for Silk Test Workbench in Oracle

This section provides instructions for creating users and granting connection rights for users. This procedure is necessary when using either Oracle OS authentication or Oracle database authentication. Separate instructions are provided for each type of authentication.

Oracle OS Authentication

Users must be created in such a way that Oracle knows they are authenticated via a DOMAIN controller.



Important:

When setting up users for Silk Test Workbench in Oracle, a schema must be also created to house the actual tables in addition to the remotely authenticated users. The schema is not domain authenticated, but is password authenticated. For more information, see [Creating the Password Authenticated Schema](#).

Users must be created within a Windows NT domain. Refer to your Microsoft Windows documentation for more information about using a Windows domain.

Users must be added to the ORA_DBA group. Use SQL*Plus or SQL*Plus Worksheet to create users. If you are not familiar with SQL*Plus, consult your Oracle documentation.

The user performing these steps must be a member of the ORA_DBA group and have SYSDBA privileges. To specify users that can access the Oracle database:

1. Start SQL*Plus or SQL*Plus Worksheet.
2. Log on as SYSTEM and connect as SYSDBA.
3. Type commands to create each user as "DOMAIN\USERNAME" IDENTIFIED EXTERNALLY, and grant connection rights for each user as "DOMAIN\USERNAME". Type DOMAIN\USERNAME in uppercase and between double quotation marks, where DOMAIN\USERNAME is each user's domain and user name. For example:

```
SQL> create user "NT-DOMAIN\JEFF" IDENTIFIED EXTERNALLY;
SQL> grant connect, resource to "NT-DOMAIN\JEFF";
```



Note: SELECT_ANY_SEQUENCE and SELECT_CATALOG_ROLE must also be granted to the user. For example:

```
SQL> grant select_any_sequence to "JEFF";
SQL> grant select_catalog_role to "JEFF";
```

Microsoft operating systems return the `DOMAIN\USERNAME` when the user is queried. If this does not match what is defined in the database, NT authentication will fail with ORA-1017.

4. Test that Windows NT authentication is set up correctly by connecting to the database via SQL*Plus. Type a "/" for the user name. Leave the **Password** field blank, and enter the host string appropriately. Click **OK**. If you are able to log on, Windows NT authentication is working properly.

Oracle Database Authentication



Important: When setting up users for Silk Test Workbench in Oracle, a schema must also be created to house the actual tables in addition to the remotely authenticated users. The schema is password authenticated. For more information, see [Creating the Password Authenticated Schema](#).

Use SQL*Plus to create users. If you are not familiar with SQL*Plus, consult your Oracle documentation. The user performing these steps must be a member of the `ORA_DBA` group and have `SYSDBA` privileges.

To specify users that can access the Oracle database:

1. Start SQL*Plus or SQL*Plus Worksheet.
2. Log on as `SYSTEM` and connect as `SYSDBA`.
3. Type commands to create each user as `"USERNAME" IDENTIFIED BY "ORACLEPASSWORD"`, and grant connection rights for each user as `"USERNAME"`. Type `USERNAME` in uppercase and between double quotation marks, where `DOMAIN\USERNAME` is each user's user name. For example:

```
SQL> create user "JEFF" IDENTIFIED BY "ORACLEPASSWORD" ;  
SQL> grant connect, resource to "JEFF" ;
```



Note: `SELECT_ANY_SEQUENCE` and `SELECT_CATALOG_ROLE` must also be granted to the user. For example:

```
SQL> grant select_any_sequence to "JEFF" ;  
SQL> grant select_catalog_role to "JEFF" ;
```

Creating the Password Authenticated Schema

To set up the password authenticated schema into which the Silk Test Workbench tables are stored, perform the following steps:



Note: The password authenticated schema should not be more than five characters in length because of Oracle character limitations in SQL series.

1. Start SQL*Plus or SQL*Plus Worksheet.
2. Log on as `SYSTEM` and connect as `SYSDBA`.
3. Type commands to create each user as `"USERNAME" IDENTIFIED BY "ORACLEPASSWORD"`, and grant connection rights for each user as `"USERNAME"`.

Type `USERNAME` in uppercase and between double quotation marks, where `USERNAME` is each user's user name. For example:

```
SQL> create user "TOM" IDENTIFIED BY "ORACLEPASSWORD" ;  
SQL> grant connect, resource to "TOM" ;
```

Preparing the Oracle Database

You must prepare your new Oracle database for use with Silk Test Workbench. This section describes how to use the **Database Maintenance** utility to populate the database with Silk Test Workbench tables.

1. Click **Start > Programs > Silk > Silk Test > Administration > Database Maintenance**. The **Database Maintenance** utility starts.
2. Click **File > New Database > Oracle**. The **Oracle Data Source Connection** dialog box opens.
3. Type the name of the new Oracle data source or click **Browse** and select a data source name from the **Select ODBC Data Source** dialog box.

4. In the appropriate boxes, type the name of the Oracle user ID, and password, and then click **Create**. The **Schema** box is filled in automatically with the same information as the User ID.

You are now ready to start Silk Test Workbench and log on.

Setting Up a SQL Server or Oracle Database Without a Domain

We strongly recommend that you use authentication within a domain when setting up an Oracle or SQL Server database with Silk Test Workbench. However, if you are not on a domain, it is still possible to set up these databases.

This section provides specific instructions for setting up a SQL Server or Oracle database with a domain.

Creating Users Without a Domain

To set up a SQL Server or Oracle database without a domain, you must first create a user account on both the client and server computers.



Note: This procedure only applies when using Windows NT authentication.

1. Access the Windows **Control Panel**, and then choose **Administrative Tools > Computer Management**
The **Computer Management** utility opens.
2. In the left pane, click **Local Users and Groups**.
3. Under **Local Users and Groups**, right-click the **Users** folder and choose **New User**. The **New User** dialog box opens.
4. Type a valid user name in the **User name** text box, and the corresponding user's full name in the **Full Name** text box.
5. Type a valid password in both the **Password** and **Confirm password** text boxes, and then click **Create**.
6. Repeat these steps on each client computer using the username and password.

Setting Up SQL Server Without a Domain

To set up SQL server without a domain:

1. Access the Windows **Control Panel**, and then choose **Administrative Tools > Computer Management**
The **Computer Management** utility opens.
2. In the left pane, expand **Local Users and Groups**, and then click **Groups**.
3. In the right pane, double-click **Users**.
The **Users Properties** dialog box opens.
4. Click **Add**.
The **Select Users, Computers, or Groups** dialog box opens.
5. Click **Advanced**, then use the **Common Queries** tab to search for users.
6. Click **Find Now**, and then select users from the list.

Alternatively, click in the **Enter the object names to select** text box and enter the [user ID] of the user you want to give access.[user ID],:

7. Click **OK** to save the user information and return to the **Users Properties** dialog box.
8. Repeat the previous steps to create additional user accounts.
9. Click **OK**.

Setting Up an Oracle Database Without a Domain

To set up Oracle without a domain, follow the procedure for creating server access for individual user accounts; however, substitute the user name you created in the procedure for creating users without a domain.

1. In the **Enter the object names to select** text box, type the user name instead of [domain name]\[user ID] or [domain name]\[group name].

The **Computer Management** utility appears.

2. Set up users.

When using SQL*Plus to create users, substitute [computer name\user name] for [domain name\user name] as shown in the following example.

```
SQL> create user "FH0002RED\USER1" IDENTIFIED EXTERNALLY;
SQL> grant connect, resource to "FH0002RED\USER1";
```



Note:

For the [computer name\user name], use uppercase and enclose in quotes.

Creating a Data Source Name Overview

On each computer that connects to the Silk Test Workbench SQL Server, Access, or Oracle database, you must create a data source name (DSN) using the ODBC utility.



Note: This step does not apply to default SQL Server Express and Access databases installed by the Silk Test Workbench installer. For these databases, a data source name is automatically created.

Creating a Data Source Name for an Access Database

On each client computer connecting to an Access database, perform the following steps to set up a DSN:

1. Access the Control Panel, and then choose **Administrative Tools > Data Sources (ODBC)**. The **ODBC Data Source Administrator** dialog box opens.
2. Click the **System DSN** tab, then click **Add**. The **Create New Data Source** dialog box opens. This dialog box lists the available ODBC drivers.
3. From the list of drivers, select the **Microsoft Access Driver** and click **Finish**. The **ODBC Microsoft Access Setup** dialog box opens.
4. In the **Data Source Name** text box, type the data source name.
Enter a logical name as this name appears as the database name in the logon dialog box.
5. In the **Description** text box, type a description for the data source.
For example, *Connection to Silk Test Workbench database*.
6. Click **Select** and browse for your Access database.
7. On the **ODBC Microsoft Access Setup** dialog box, click **OK**.
8. On the **ODBC Administrator** dialog box, click **OK** to complete the process.

Creating a Data Source Name for a SQL Server Database



Note: Silk Test Workbench cannot use 64-bit DSNs. To create a DSN for a 64-bit machine, click **Start > Silk > Silk Test > Administration > Data Sources (ODBC)** and create a 32-bit DSN. You can also use the WOW64 tools located at `C:\WINDOWS\SysWOW64\odbcad32.exe`.

On each client computer connecting to a SQL server database, perform the following steps to set up a DSN:

1. Access the Control Panel, and then choose **Administrative Tools > Data Sources (ODBC)**. The **ODBC Data Source Administrator** dialog box opens.
2. Click the **System DSN** tab, then click **Add**. The **Create New Data Source** dialog box opens. This dialog box lists the available ODBC drivers.
3. From the list of drivers, select the **SQL Native Client** and click **Finish**. The **Create a New Data Source to SQL Server** dialog box opens.
4. In the **Name** box, type the data source name.
Enter a logical name as this name appears as the database name in the logon screen.
5. In the **Description** text box, type a description for the data source.
For example, `Connection to Silk Test Workbench database`.
6. In the **Server** text box, enter the server name or select it from the drop-down list.
7. Click **Next**.
8. Perform one of the following:
 - If user(s) using the DSN to access the SQL Server database are connecting with non-native credentials, select the **With Windows authentication** using the network login ID option.
 - If user(s) using the DSN to access the SQL Server database are connecting with native authentication, select the **With SQL Server authentication using a login ID and password entered by the user** option. Make sure the **Connect to SQL Server to obtain the default settings for the additional configuration options** check box is checked. Type the users native SQL Server logon credentials in the **Login ID** and **Password** text boxes.
9. Click **Next**.
10. Check the **Change the default database to** check box, and then select your database name from the list.
11. Accept all the other entries and click **Next** until the last panel in the wizard appears.
12. Accept the defaults and click **Finish**.
13. To test the connection, click **Test Data Source**. The **SQL Server ODBC Data Source Test** dialog box opens.
14. Click **OK**.
The **ODBC Data Source Administrator** dialog box reappears. The newly created data source appears in the **System Data Sources** list.
15. Click **OK**.

Creating a Data Source Name for an Oracle Database



Note: Silk Test Workbench cannot use 64-bit DSNs. To create a DSN for a 64-bit machine, click **Start > Silk > Silk Test > Administration > Data Sources (ODBC)** and create a 32-bit DSN. You can also use the WOW64 tools located at `C:\WINDOWS\SysWOW64\odbcad32.exe`.

On each client computer connecting to an Oracle database, perform the following steps to set up a DSN:

1. Access the Control Panel, and then choose **Administrative Tools > Data Sources (ODBC)**. The **ODBC Data Source Administrator** dialog box opens.
2. Click the **System DSN** tab, then click **Add**. The **Create New Data Source** dialog box opens. This dialog box lists the available ODBC drivers.
3. From the list of drivers, select the appropriate Oracle ODBC driver for the version of Oracle database being used (not the Microsoft ODBC for Oracle driver), and then click **Finish**. The **Oracle ODBC Driver Configuration** dialog box opens.
4. In the **Oracle Data Source Name** text box, type the data source name.
Enter a logical name as this name appears as the database name in the logon dialog box.
5. In the **Description** text box, type a description for the data source.
For example, `Connection to Silk Test Workbench database`.
6. In the **TNS Service Name** text box, select the service name for the database you want to connect to in the format `ORACLE_SID.DOMAIN`, where `ORACLE_SID` is the Oracle SID you assigned to the database upon creation and domain is the domain to which you are connecting.
7. If using Oracle authentication, type a valid user ID for the database being connected to in the **User ID** text box. Otherwise, leave the **User ID** text box empty.
8. To test the connection, click **Test Connection**.



Note: When using Oracle database authentication, type a username, and then a password. For Oracle OS authentication, do not specify a username.

A message box appears stating the connection was successful.

9. Click **OK**.

Connecting to a Database Overview

After installing Silk Test Workbench and configuring a database, you must create a database connection. This connection defines the relationship between a Silk Test Workbench database and the local Silk Test Workbench installation. This section contains topics describing how to log on and create a database connection.

Logging On

1. Click **Start > Programs > Silk > Silk Test > Clients > Silk Test Workbench**. Silk Test Workbench starts and displays the **Login to SilkTest Workbench** dialog box.
2. From the **Authentication** list box, select if you want to use the **Silk Test Workbench** authentication, or the **Windows** authentication.



Note: You can use the **Windows** authentication only for users that were added to the Silk Test Workbench users by using **Tools > Administration**.

3. If you are using the **Silk Test Workbench** authentication, type a user name in the **User Name** field and a password in the **Password** field. If you are using the **Windows** authentication, you do not have to provide a user name and password.

If you are using Silk Test Workbench for the first time, an administrative user name and password may be required. The default user name is `Admin` and the default password is `admin`. Change this password after logging on to prevent unauthorized access. You can change your logon password at any time.

4. Select the database to use from the **Database** list.
For a database to appear in the **Database** list, you must first configure its database connection for use. To configure a database connection, click **Configure** on the **Logon** dialog box.
5. Click **OK**. The **Start Screen** opens.

Changing Your Logon Password

Use the following procedure to change your logon password.

1. Click **Tools > Change Password**. The **Change Password** dialog box opens.
2. Change your password and then click **OK**. Changes take effect the next time the User ID is used to log on.


Configuring a Database Connection

Before you can use a database with Silk Test Workbench, you must configure its database connection. The configuration process consists of using the **Configure Database Connection** dialog box to perform the following tasks:

- Specify the database connection data required to initiate the database connection.
- Verify the connection to the database.
- Save the database connection data.

All configured database connections appear in the **Database** list that is located on the Silk Test Workbench dialog box.

You can also use the **Configure Database Connection** dialog box to view, edit, and remove any existing configured database connections.

 **Note:** Before configuring a database connection for use with Silk Test Workbench, you must create and configure a database instance and ODBC Data Source Name (DSN).

 **Note:** Silk Test Workbench cannot use 64-bit DSNs. To create a DSN for a 64-bit machine, click **Start > Silk > Silk Test > Administration > Data Sources (ODBC)** and create a 32-bit DSN. You can also use the WOW64 tools located at `C:\WINDOWS\SysWOW64\odbcad32.exe`.

1. Click **Configure** on the **Login to Silk Test Workbench** dialog box. The **Configure Database Connection** dialog box opens.
2. In the **Data Source Type** section, select the type of data source.
3. From the **Select Data Source** list, select from the list of available DSNs.
4. Check the **Use as a Silk Test Workbench database** check box to add the selected DSN to the list of configured database connections that appear in the **Database** list on the **Login to Silk Test Workbench** dialog box.

You must check this check box when configuring a database connection for the first time. For existing configured database connections, unchecking the **Use as a Silk Test Workbench database** check box and clicking **Apply** removes the selected DSN from the **Database** list on the dialog box. Silk Test Workbench does not retain the associated database connection data.

5. In the **Database Settings** section, specify the appropriate information for the selected DSN. For Access, the **Database** box is read-only and displays the location of the database file. This value is read directly from the ODBC DSN. The other **Database Settings** text boxes are not applicable for Access and are disabled. For Oracle, the **Server** text box is read-only and displays only the database name. This value is read directly from the ODBC DSN.
6. In the **Database** box, type the appropriate value. For SQL Server/MSDE, the **Database** text box is modifiable and allows you to type the appropriate database name.
7. In the **Owner** box, type the appropriate value.
8. Select a type of authentication.

Authentication options only apply to Oracle or SQL Server/MSDE databases. You can choose to use either Windows NT authentication or authenticate using the database's native authentication capabilities. When selecting database authentication, you must provide the user name and password in the appropriate text boxes.

9. Click **Validate** to verify that you can connect to the database using the specified database connection data.
10. Click **Apply** to save the database connection data.
11. Click **Close** to dismiss the dialog box.

Index

A

- admin permissions
 - required 7
- administrator privileges
 - required 7

C

- changing password
 - logon 51
- configuring
 - SQL Server 39
- configuring database connection 51
- creating
 - DSN 48
- creating a Data Source Name (DSN)
 - Access 48
 - Oracle 49
 - SQLServer 49

D

- Data Source Name (DSN) 48
- database connection
 - configuring 51
- downloading executable file 13
- DSN
 - Access 48
 - Oracle 49
 - overview 48
 - SQL Server 49

E

- Eclipse plug-in 21, 23
- error codes 37

G

- generating license policies 10
- Green Mountain Outpost (GMO) application 7

H

- host IDs
 - finding 10

I

- installing
 - agents 28
 - overview 5
 - process overview 13
 - silent mode 31, 36, 37
 - Silk Test 16

- Silk Test standard suite 14
- Silk Test Workbench 19
- Silk4J 21, 23
- Silk4NET 24, 26
- SilkTest 26
- installing from CD
 - silent mode 35
- installing in silent mode
 - setting up installer 33
 - Web installer 35
- Insurance Company Web application 7

L

- license servers
 - requirements 10
- licensing
 - available license types 9
 - generating policies 10
 - overview 10
 - test connections 12
- log in
 - Silk Test Workbench 50
- logging on
 - Silk Test Workbench 50
- logon password
 - changing 51

O

- Oracle
 - authentication method 41
 - creating a new database 43
 - creating server access for users 44
 - creating the ORA_DBA group 44
 - OS authentication
 - setting up users 42
 - overview 41
 - password authenticated schema 46
 - preparing database for client connectivity 44
 - preparing the database 46
 - setting up Oracle authentication 43
 - setting up the client 44
 - setting up users 42, 45
 - setting up without a domain 47, 48
- overview
 - configuring an Oracle database 41
 - installing 5
 - items installed 7

R

- Rumba
 - enabling and disabling support 23

S

- sample applications 7

- setting up a database without a domain
 - creating users 47
- setting up without a domain
 - setting up Oracle 48
 - SQL Server 47
- silent mode
 - creating properties file 31
 - installing 31, 36, 37
 - installing from CD 35
 - installing with Web installer 35
 - setting up installer 33
 - uninstalling 38
- Silk Meter
 - installing 10
 - installing on license servers 11
 - testing connections 12
 - uninstalling 11
- Silk Test Workbench
 - installing 19
- Silk4J
 - installing manually 23
- Silk4NET
 - installing manually 26

- SQL Server
 - configuring 39
 - creating a new SQL Server admin user 39
 - creating a new SQL Server database 39
 - preparing the database 41
 - setting up users 40
 - setting up without a domain 47

T

- TEMP environment variable 13
- tutorials 38

U

- uninstalling
 - SilkTest 31

V

- Visual Studio plug-in 24, 26